

Developer's Guide

Version 6.3

December 12, 2018

Copyright © 2018 Attunity Ltd. All rights reserved.

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, endpoints, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Attunity license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software—Restricted Rights (June 1987). Attunity Ltd., 70 Blanchard Road, Burlington, MA 01803

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Attunity is a registered trademark of Attunity Ltd and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Attunity is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Attunity is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Attunity is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Contents

1 | Introduction

2 | AEM REST SDK

Prerequisites	14
Standards and Conventions	14
Authentication and Authorization	14
Error Handling	15
AemLogin	16
AemLogout	18
AemPutServerLicense	19
AemGetServerDetails	21
AemPutServer	26
AemPutServerAcl	31
AemGetServer	39
AemGetServerAcl	43
AemGetServerList	49
AemDeleteServer	52
AemDeleteServerAcl	53
AemGetTaskList	55
AemGetTaskDetails	58
AemDeleteTask	67
AemExportTask	70
AemImportTask	71
AemStopTask	74
AemRunTask	76
AemGetEndpointList	82
AemDeleteEndpoint	85
AemExportAll	86
AemImportAll	88
AemReloadTable	91
AemTestEndpoint	92

Parameters	94
3 AEM .NET SDK	
Prerequisites	100
General Prerequisites	100
.NET SDK Prerequisites	100
How To	100
Creating Credentials	101
Creating a Client Object	101
Using Client Methods to Get/Set Data on AEM	101
Authentication and Authorization	101
Error Handling	101
PutServerLicense	103
Syntax	103
Parameters	103
Return Values	104
Errors	104
GetServerDetails	104
Syntax	104
Parameters	105
Return Values	105
PutServer	109
Syntax	109
Parameters	109
Return Values	110
Errors	110
PutServerAcl	111
Syntax	112
Parameters	113
Return Values	113
Errors	113
GetServer	115
Syntax	115
Parameters	115
Return Values	115
Errors	116
GetServerAcl	116

Syntax	116
Parameters	116
Return Values	117
GetServerList	118
Syntax	118
Parameters	118
Return Values	118
DeleteServer	120
Description	120
Syntax	120
Required User Role: Admin on server.Syntaxpublic void DeleteServer(string server);	120
Parameters	120
Return Values	120
DeleteServerAcl	121
Syntax	121
Parameters	121
Return Values	121
Errors	121
GetTaskList	122
Syntax	122
Parameters	122
Return Values	122
Errors	123
GetTaskDetails	123
Syntax	124
Parameters	124
Return Values	124
DeleteTask	132
Syntax	132
Parameters	133
Errors	133
ExportTask	133
Syntax	134
Parameters	134
Return Values	134
Errors	134
ImportTask	134

Syntax	135
Parameters	135
Return Values	135
Errors	135
StopTask	136
Syntax	137
Parameters	137
Return Values	137
RunTask	138
Syntax	138
Parameters	138
Return Value	140
Errors	140
GetEndpointList	141
Syntax	141
Parameters	142
Return Values	142
Errors	142
DeleteEndpoint	143
Description	143
Syntax	143
Parameters	143
Return Values	144
Errors	144
ExportAll	144
Syntax	144
Parameters	144
Return Values	145
Errors	145
ImportAll	145
Syntax	145
Parameters	146
Return Values	146
Errors	146
ReloadTable	146
Syntax	147
Parameters	147
Return Values	147

Errors	147
TestEndpoint	148
Syntax	148
Parameters	148
Return Values	148
Errors	149
Parameters	149

4 | AEM Python SDK

Prerequisites	154
General Prerequisites	154
Python 2.7 Prerequisites	154
Python 3.7 Prerequisites	154
How To	154
Authentication and Authorization	155
Error Handling	155
put_server_license	157
Syntax	157
Parameters	158
Return Values	158
Errors	158
get_server_details	158
Syntax	158
Parameters	159
Return Values	159
put_server	162
Syntax	163
Parameters	163
Return Values	164
Errors	164
put_server_acl	165
Syntax	166
Parameters	167
Return Values	167
Errors	167
get_server	169
Syntax	169

Parameters	169
Return Values	169
Errors	170
get_server_acl	170
Syntax	170
Parameters	171
Return Values	171
get_server_list	172
Syntax	172
Parameters	172
Return Values	172
delete_server	174
Description	174
Syntax	174
Parameters	174
Return Values	174
delete_server_acl	175
Syntax	175
Parameters	175
Return Values	175
Errors	175
get_task_list	176
Syntax	176
Parameters	176
Return Values	176
Errors	178
get_task_details	178
Syntax	178
Parameters	178
Return Values	178
delete_task	185
Syntax	185
Parameters	185
Return Values	185
Errors	186
export_task	186
Syntax	186
Parameters	187

Return Values	187
Errors	187
import_task	187
Syntax	188
Parameters	188
Return Values	188
Errors	188
stop_task	189
Syntax	189
Parameters	190
Return Values	190
run_task	191
Syntax	191
Parameters	191
Return Value	193
Errors	193
get_endpoint_list	194
Syntax	194
Parameters	195
Return Values	195
Errors	195
delete_endpoint	196
Description	196
Syntax	196
Parameters	196
Return Values	196
Errors	196
export_all	197
Syntax	197
Parameters	197
Return Values	197
Errors	197
import_all	198
Syntax	198
Parameters	198
Return Values	199
Errors	199
reload_table	199

Syntax	199
Parameters	200
Return Values	200
Errors	200
test_endpoint	200
Syntax	200
Parameters	201
Return Values	201
Errors	201
Parameters	202

1 | Introduction

The AEM SDKs provide an programmatic interfaces for performing tasks typically carried out using the AEM web application, such as:

- » Viewing a list of tasks for a server
- » Viewing details for a particular task
- » Stopping a task
- » Running a task
- » Exporting all definitions from the requested server repository on the selected server
- » Importing the JSON definitions provided in the request body into the requested server repository on the selected server
- » Reloading a table
- » Exporting a task
- » Importing a task
- » Testing an endpoint's connectivity and configuration

The AEM SDKs allows other systems to interact with AEM, for example to display data about one or more tasks in a user's dashboard. They also offers a quick and easy way of running batch operations.

Using an SDK requires basic familiarity with web services, Replicate, and AEM.

Note The following methods are supported with Replicate tasks only:

- » AemImportAll
- » AemExportAll
- » AemExportTask
- » AemTestEndpoint
- » AemGetEndpointList
- » AemDeleteEndpoint
- » AemGetTaskList
- » AemImportTask
- » AemGetTaskDetails
- » AemStopTask
- » AemRunTask
- » AemDeleteTask
- » AemReloadTable

In this chapter:

2 | AEM REST SDK

This chapter explains how to use the AEM REST SDK and the lists the available methods.

In this chapter:

[Prerequisites](#)

[Standards and Conventions](#)

[Authentication and Authorization](#)

[Error Handling](#)

[AemLogin](#)

[AemLogout](#)

[AemPutServerLicense](#)

[AemGetServerDetails](#)

[AemPutServer](#)

[AemPutServerAcl](#)

[AemGetServer](#)

[AemGetServerAcl](#)

[AemGetServerList](#)

[AemDeleteServer](#)

[AemDeleteServerAcl](#)

[AemGetTaskList](#)

[AemGetTaskDetails](#)

[AemDeleteTask](#)

[AemExportTask](#)

[AemImportTask](#)

[AemStopTask](#)

[AemRunTask](#)

[AemGetEndpointList](#)

[AemDeleteEndpoint](#)

[AemExportAll](#)

[AemImportAll](#)

[AemReloadTable](#)

[AemTestEndpoint](#)

[Parameters](#)

Prerequisites

Before using the AEM REST API, make sure that:

- » Attunity Enterprise Manager has been installed.
- » The AEM service is active.
- » The relevant permissions have been granted.

Standards and Conventions

The API is based on the following standards:

- » Names: Camel Case, such as GetTaskList
- » Date and time format: ISO 8601 (YYYY-MM-DD HH:MM:SS), in UTC (Universal Time Coordinated)
Example: 2007-04-05T14:30:25 (implicitly interpreted as UTC without the explicit trailing Z).
- » Standard URL format: api/v1/URL

In addition, this section uses the following conventions:

- » Parameters in examples appear in curly brackets as {xx} and should be replaced with an actual value. An example of a parameter is {server}, which should be replaced by the server name or IP address of the machine where Replicate is installed. For a list of parameters, see [Parameters](#).

All examples in this chapter use cURL as the HTTP engine.

In terms of forward and backward compatibility of the AEM REST API, the caller should expect future releases to add new optional request parameters and additional data items in responses.

Authentication and Authorization

The AEM REST API uses the BASIC HTTP authorization scheme to authenticate callers and create a client session. A client session is established using the [AemLogin](#) method, which returns the special header "EnterpriseManager.APISessionID" with a value (session token) that needs to be sent as a request header in following requests.

A session token expires 5 minutes after the last request. After the session expires, the caller must re-authenticate to establish a new session.

Authorization for performing a specific REST request relies on permission, assigned to the authenticated user either directly or by means of group membership. Each REST request requires a minimum role, which is specified in the section describing the request.

Error Handling

An error response has the following structure:

```
{
  "error_code": "code", "error_message": "message"
}
```

This section lists the generic messages that apply to most of the API functions. Errors that are specific to a particular API function appear in the section for that API function.

Error Code	Message	Description
UNAUTHORIZED_REQUEST	Unauthorized Request.	The user is not authorized to perform the requested action (e.g. deleting a task).
INVALID_SESSION_ID	The session has expired or the session ID is not valid.	Session expired or invalid.
DESERIALIZE_TO_TYPE	Failed to deserialize json to type {type}: {message}	Returned when the JSON format is invalid.
AEM_SERVER_NOT_FOUND	The requested server {server} could not be found.	The requested server cannot be found.
AEM_SERVER_NOT_MONITORED	The requested server {server} is not monitored.	The requested server is not being monitored and thus the information is not accessible.
AEM_SERVER_NOT_CONNECTED	The requested server "{server}" cannot be reached at this time. Message: {message}	The desired information cannot be retrieved as the requested server is not connected.
AEM_SERVER_LICENSE_EXPIRED	The license for requested server {server} has expired.	The requested server license has expired.
AEM_SERVER_INVALID_LICENSE	The license for requested server {server} is not valid.	The requested server license is not valid.
LICENSE_NOT_FOUND	You need to register a Replication Management license in order to use Attunity Enterprise Manager. To register or obtain a license, open the Attunity Enterprise Manager console and follow the instructions.	Replication Management license was not found. For a user who is permitted to Register AEM license.
LICENSE_NOT_FOUND_	An Enterprise Manager Admin needs to register a Replication	Replication Management license was not found. For a user who is

Error Code	Message	Description
CONTACT_ADMIN	Management license before you can use the product. To obtain a license, contact your Attunity Sales Representative with the Enterprise Manager machine name (which is displayed when you open the Enterprise Manager console).	NOT permitted to Register AEM license.
LICENSE_EVALUATION_EXPIRED	{Module} evaluation license has expired.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
LICENSE_TERM_EXPIRED	{Module} license has expired.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
LICENSE_INVALID_SIGNATURE	The {Module} license signature is invalid.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
LICENSE_HOST_MISMATCH	The host name in the {Module} license does not match the Enterprise Manager machine name.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
AEM_MISSING_FIELD	The "{fieldName}" field is missing from the request.	When a mandatory field is missing from the request or appears empty

AemLogin

General

Title	AemLogin
URL	https://{host}/attunityenterprisemanager/api/v1/login
Description	Authenticates an API caller with AEM and acquires a session token to be used with API method calls. The server requests client

	authentication.
HTTP Method	GET
Required User Role	Viewer

Request Parameters

Location	URL Param Name	Required	Example
URL	host [string]	Yes	computer.network.net
Header	user@domain:password converted to base 64 [string]	Yes	c27kc2Rmc27k

Response Header

URL Param Name	Description
EnterpriseManager.APISessionID	Identifier to be used to get authorization to run API functions on AEM

cURL Example

Request	<pre>curl -i -k --header "Authorization: Basic cWFAcWE6cWE=" https://computer.network.net/attunityenterprisemanager/ api/v1/login</pre> <p>Enter host password for user name@domain.</p>
Response	<pre>HTTP/1.1 200 OK Content-Length: 0 Content-Type: text/html Server: Microsoft-HTTPAPI/2.0 EnterpriseManager.APISessionID: J3cKzWibi_w6Fr1G-t003Q Date: Mon, 26 Dec 2016 17:02:01 GMT</pre>

Error Response

HTTP Code	AEM Code	Text	Description
401	UNAUTHORIZED_REQUEST	Unauthorized Request.	The request was not authorized.

AemLogout

General

Title	AemLogout
URL	https://{host}/attunityenterprisemanager/api/v1/logout
Description	End a session
HTTP Method	GET
Required User Role	Viewer

Request Parameters

Location	URL Param Name	Required	Example
URL	host [string]	Yes	computer.network.net
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_ KvjEUFROvfHF5KGrw

cURL Example

Request	<pre>curl -i -k --header "EnterpriseManager.APISessionID: wCo0_ KvjEUFROvfHF5KGrw A" https://computer.network.net/attunityenterprisemanager/ api/v1/logout</pre>
Response	<pre>Header: HTTP/1.1 200 OK Content-Length: 0 Content-Type: text/html Server: Microsoft-HTTPAPI/2.0 Date: Tue, 27 Dec 2016 08:00:27 GMT</pre>

AemPutServerLicense

General

Title	AemPutServerLicense
URL	https://[host]/attunityenterprisemanager/api/v1/servers/[server]/license/def
Description	Registers a license on a specific server via AEM.
HTTP Method	PUT
Required User Role	Admin on the specified server

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	The name of the server in AEM: myreprsv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Request Body

The license to register on the server [stream].

This is the license that was provided by your Attunity Sales Representative.

Expected format: Text or JSON.

Currently refers to the Replicate license only.

cURL Example

Request `curl -i -k -X PUT --header "EnterpriseManager.APISessionID:wCo0_KvjEUFROvfHF5KGrw" --header "Content-Length: 324" "https://computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1/license/def" -T "C:\license_exp2018-02-07_ser90000319.txt"`

Request #
Body # Temporary license for development
(content of "C:\license_exp2018-02-07_ser90000319.txt") #
license_type=evaluation_license
licensed_to=Attunity Internal - Attunity Replicate Development
licensed_by=Miki
serial_no=2333
expiration_date=2018-01-31
source_types=
target_types=
features=manager
version=5.5.0.0
issue_date=2017-11-01
checksum=C2855-R5J8F-JF8RQ-C3K7K

Response Header:

HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 38
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 16:31:01 GMT

Error Response

All of the [general errors](#) as well as the errors listed in the table below.

HTTP Code	AEM Code	Text	Description
500	AEM_PUT_SRV_LIC_INNER_ERR	Failed to put license for server "{server}". Error: "{message}"	Returned if AEM encounters an error/exception when trying to register the license on the specified server.
500	AEM_SRV_LIC_INVALID_FORMAT	The license file format is corrupt.	Returned when the contents of the license file are invalid.

AemGetServerDetails

General

Title	AemGetServerDetails
URL	https://{host}/attunityenterprisemanager/api/v1/servers/[server]
Description	Retrieves details about the specified server.
HTTP Method	GET
Required User Role	Viewer

Request Parameters

Location	Name	Required	Example
URL	host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Response Body

```

Body    {
        "serverDetails":{
            "$type":"{string}",
            "name":"{string}",
            "description":"{string}",
            "configuration":{
                "host":"{string}",
                "platform":"{enum server_platform}",
                "port":"{string}",
                "username":"{string}"
            },
            "state":"{enum server_state}",
            "message": "{string}",
            "version": "{string}",
            "license":{
                "issue_date":"{string}",
                "state":"{enum license_state}",
                "expiration":"{string}",
                "days_to_expiration":"{int32}"
            },
            "last_connection":"{string}",
            "task_summary":{
                "total":"{int32}",
                "running":"{int32}",
                "stopped":"{int32}",
                "recovering":"{int32}",
                "error":"{int32}"
            },
            "resource_utilization":{
                "disk_usage_mb":"{int64}",
                "memory_mb":"{int64}",
                "attunity_cpu_percentage":"{int32}",
                "machine_cpu_percentage":"{int32}"
            },
        },
    }
}

```

Response Parameters

Name	Description
\$type	The server's type, which can either be

Name	Description
	ReplicateServerDetails OR ComposeServerDetails.
Name	The name of the server in AEM.
Description	The server description
configuration	
host	The host name or IP address of the Replicate/Compose Server machine.
platform	The platform on which the Replicate/Compose Server machine is installed.
port	The port through which the Replicate/Compose Server machine is accessed.
user name	The user name for connecting to the Replicate/Compose Server machine.
State	The current monitoring state of the Replicate/Compose Server machine.
message	The error message if AEM fails to connect to the Replicate/Compose Server machine.
version	The Replicate/Compose Server version.
license	
issue_date	When the license was issued.
state	The current license state (e.g. valid, expired, etc.).
expiration	The expiration date of the server license.
days_to_expiration	The number of days left before the license expires.
last_connection	The date and time of the last successful sync/retrieval of tasks and messages.
task_summary	
total	The total number of tasks, regardless of state.
running	The number of running tasks.
stopped	The number of stopped tasks.
recovering	The number of recovering tasks.
error	The number of tasks that encountered a fatal error.
resource_utilization	

Name	Description
disk_usage_mb	The amount of disk space that the server is currently consuming, in MB. This is the sum of disk usage for all tasks on this server.
memory_mb	The amount of memory that the server is currently consuming, in MB. This is the sum of memory usage for all active tasks on this server, excluding stopped tasks.
attunity_cpu_percentage	The current CPU usage of the Replicate server process + all task processes.
machine_cpu_percentage	The current total CPU usage of all the processes running on the machine.

Notes

- » The return value -1 means N/A.
- » Parameters related to Disk, Memory, Attunity CPU, and Machine CPU usage are not available for Compose servers. For Compose servers, these parameters will be returned as -1.
- » Parameters related to Attunity CPU and Machine CPU usage are only available for Replicate 6.2 and above. For earlier Replicate versions, these parameters will be returned as -1.
- » For servers that are in an error state or not monitored, parameters related to Disk and Memory usage will be returned as -1.

cURL Example

Request `curl -i -k --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGrw" https://computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1`

Response Headers:
 HTTP/1.1 200 OK
 Cache-Control: no-cache, no-store
 Content-Length: 1658
 Content-Type: application/json; charset=utf-8
 Server: Microsoft-HTTPAPI/2.0
 Date: Mon, 26 Dec 2016 13:18:27 GMT
 Payload:
 {
 "serverDetails":{
 "\$type": "ReplicateServerDetails",
 "name":"myreprsv1",
 "description":"My daily replication tasks",
 "configuration":{
 "host":"computer.network.net",
 "platform":"WINDOWS",
 "port":"443",
 "username":"Administrator"
 },
 "state":"MONITORED",
 "message": "",
 "version": "5.2.0.156",
 "license":{
 "issue_date":"2016-12-31",
 "state":"LICENSE_VALID",
 "expiration":"2017-12-31",
 "days_to_expiration":"30"
 },
 "last_connection":"2016-12-18T02:23:30",
 "task_summary":{
 "total":50,
 "running":20,
 "stopped":10,
 "recovering":12,
 "error":8
 },
 "resource_utilization":{
 "disk_usage_mb":500,
 "memory_mb":112832,
 "attunity_cpu_percentage":30,
 }
 }

```

        "machine_cpu_percentage":50
    },
}

```

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_SERVER_NOT_FOUND	Replicate server {server} could not be found.	Server name unknown to AEM.
403	See Error Handling .		
440	See Error Handling .		

AemPutServer

General

Title	AemPutServer
URL	https://[host]/attunityenterprisemanager/api/v1/servers/[server]/def
Description	<p>Adds a new Replicate/Compose Server or updates the server definition (Connection Properties) if the specified server already exists.</p> <p>This method can be used together with <code>AemGetServer</code> in order to update the connection properties of an existing server. First call <code>AemGetServer</code>, then edit the returned properties as required, and finally, call <code>AemPutServer</code>.</p>
HTTP Method	PUT
Required User Role	<p>For adding a new server - Admin on all servers.</p> <p>For updating an existing server - Admin on the specified server.</p>

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Request Body

```

Body      {
    "$type": "{string}",
    "name": "{string}",
    "description": "{string}",
    "host": "{string}",
    "port": "{string}",
    "username": "{string}",
    "password": "{string}",
    "monitored": "{bool}"
}

```

Request Parameters

Name	Description
\$type	The server's type: Can either be <code>AemReplicateServer</code> or <code>AemComposeServer</code> .
name	The name of the server. For details of what constitutes a valid server name, see AEM_INVALID_NAME .
description	The description of the server. For details of what constitutes a valid description, see AEM_INVALID_DESC .
host	The host name or IP address of the server. For details of what constitutes a valid host name, see AEM_INVALID_HOST .
port	The port through which the server is accessed.
username	The user name to connect to the server. The specified user must be a server administrator.

Name	Description
	For details of what constitutes a valid user name, see AEM_INVALID_USERNAME .
password	<p>The password to connect to the server.</p> <div data-bbox="516 401 1393 640" style="background-color: #e0f2f7; padding: 10px; border-radius: 5px;"> <p>Note Within a session, the password identifier (GUID) that is returned by <code>AemGetServer</code> can be used in this request to indicate that the password should remain unchanged.</p> <p>The password identifier returned by <code>AemGetServer</code> must be used in the same session, otherwise an error will occur.</p> </div>
monitored	Whether to retrieve tasks and messages from this server or not. The default is true.

cURL Example

Request `curl -i -k -X PUT --header "EnterpriseManager.APISessionID:wCo0_KvjEUFROvfHF5KGrw" --header "Content-Length: 242" https://computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1/def -T "C:\myreprsv1.json"`

Request Body {
(content of
"C:\myreprsv1
.json")

```
    "$type": "AemReplicateServer",  
    "name": "myreprsv1",  
    "description": "replicate for business",  
    "host": "rep2018r2gs7.qa.int",  
    "port": "443",  
    "username": "administrator",  
    "password": "pass123",  
    "monitored": true  
}
```

Response Headers:
HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 38
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 13:18:27 GMT

Error Response

All of the [general errors](#) as well as the errors listed in the table below.

HTTP Code	AEM Code	Text	Description
500	DESERIALIZE_TO_TYPE	"Failed to deserialize json to type AemServer: {message}"	Returned when the JSON format is invalid format. For example, such an error will be returned if the JSON contains an unknown role.
500	AEM_PUT_SERVER_INNER_ERR	Failed to put server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to PUT the server.
500	AEM_INVALID_SERVER_TYPE	Server type {ServerType} for server "{ServerName}" is not valid.	Returned when the an invalid server type is specified.
500	AEM_NAME_URL_MISMATCH	The name of the server in the request does not match the one that is specified in the URL.	Returned when the name of the server in the request does not match the one that is specified in the URL.
500	AEM_EMPTY_HOST	The host is missing from the request.	Returned when the host is missing from the request.
500	AEM_EMPTY_PORT	The port is missing from the request.	Returned when the port is missing from the request.
500	AEM_EMPTY_USERNAME	The username is missing from the request.	Returned when the user name is missing from the request.
500	AEM_EMPTY_PASSWORD	The password is missing from the request.	Returned when the password is missing from the request.
500	AEM_INVALID_PORT	The port is invalid.	Returned when the specified port is not valid.
500	AEM_INVALID_USERNAME	The user name is invalid.	Returned when the

HTTP Code	AEM Code	Text	Description
		User names cannot exceed 104 characters and can contain all Unicode characters except for the following characters: Forward slash (/), Left square bracket ([), Right square bracket (]), Colon (:), Semicolon (;), Vertical bar (), Equal sign (=), Plus sign (+), Asterisk (*), Question mark (?), Left angle bracket (<), Right angle bracket (>), Double quote (\").	specified user name is not valid.
500	AEM_INVALID_DESC	The description is invalid. Descriptions cannot exceed 250 characters.	Returned when the description exceeds 250 characters.
500	AEM_INVALID_HOST	The host is invalid. Hosts cannot exceed 64 characters and can only contain letters (a-z or A-Z), digits, spaces, dots (.), dashes (-), and underscores (_).	Returned when the server host name exceeds 64 characters or contains invalid characters.
500	AEM_INVALID_NAME	The name of the server is invalid. Server names cannot exceed 64 characters and can only contain letters (a-z or A-Z), digits, spaces, dots (.), dashes (-), and underscores (_).	Returned when the server name exceeds 64 characters or contains invalid characters.
500	AEM_HOST_PORT_ALREADY_EXIST	Host {name/IP} and port {number} are already in use by another server.	Returned when both the server host name/IP address and the server port are already in use by another server.

AemPutServerAcl

General

Title	AemPutServerAcl
-------	-----------------

URL	https://[host]/attunityenterprisemanager/api/v1/servers/[server]?action=acl
Description	<p>Puts an explicit ACL for a specific server in AEM.</p> <p>The method will replace any existing explicit ACL with the ACL in the request.</p> <p>The request also includes a Boolean flag for specifying if the server should inherit ACLs from its ancestors (in addition to its explicitly defined ACLs) or not.</p> <p>The inherited ACLs (i.e. the ACLs of the server's ancestors) are not affected by this method.</p> <p>The <code>AemPutServerAcl</code> can be used together with the <code>AemGetServerAcl</code> method in order to update an existing server's ACL. First call <code>AemGetServerAcl</code>, then edit the returned roles as required, and finally, call <code>AemPutServerAcl</code>.</p>

Behavior when putting a partial request:

When the request body includes only some of the roles (as opposed to all four of them), only the roles specifically defined in the request body will be set on the server; roles that are missing or empty will be inherited, but only if the following are true:

- » The `disable_inheritance` flag is set to "True".
- » The roles that are missing/empty in the request are defined for the ancestors.

Behavior on conflicts:

If the `disable_inheritance` flag is set to "False" and the explicit roles in the request conflict with existing inherited roles, then the explicit roles will take precedence. For example, if the request defines user A as a Viewer on **MyServer** and user A is also defined as an Admin on All Servers, then user A will be defined as an Admin on All Servers but as a Viewer on **MyServer**.

Note The user permissions in AEM are completely independent of the user permissions in Replicate. Consequently, `AemPutServerAcl` will affect the server's AEM user permissions, but will *not* affect Replicate's user permissions.

Moreover, when performing an operation via AEM, the user permissions defined for the server entity in AEM apply, whereas when performing an operation directly via the Replicate Console, the user permissions defined in Replicate apply.

Note Defining the same user/group in different roles is not allowed. However, if the same user or group is defined in different roles but with a different case (e.g. Mike vs. mike or Analysts vs. ANALYSTS), no error will be returned and the strongest role will take precedence.

HTTP Method	PUT
Required User Role	Admin on the specified server

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Request Body

```
{
  "admin_role": {
    "users": [ { "name": "{string}" }, { "name": "{string}" }, ... ],
    "groups": [ { "name": "{string}" }, { "name": "{string}" }, ... ]
  },
  "designer_role": {
    "users": [ { "name": "{string}" }, { "name": "{string}" }, ... ],
    "groups": [ { "name": "{string}" }, { "name": "{string}" }, ... ]
  },
  "operator_role": {
    "users": [ { "name": "{string}" }, { "name": "{string}" }, ... ],
    "groups": [ { "name": "{string}" }, { "name": "{string}" }, ... ]
  },
  "viewer_role": {
    "users": [ { "name": "{string}" }, { "name": "{string}" }, ... ],
    "groups": [ { "name": "{string}" }, { "name": "{string}" }, ... ]
  },
  "disable_inheritance": "{bool}"
}
```

Request Parameters

Name	Description
admin_role	
users	An array of users assigned as Admins on the server.
name	A single Admin user.
groups	An array of groups assigned as Admins on the server.
name	A single Admin group.
designer_role	
users	An array of users assigned as Designers on the server.
name	A single Designer user.
groups	An array of groups assigned as Designers on the server.
name	A single Designer group.
operator_role	
users	An array of users assigned as Operators on the server.
name	A single Operator user.
groups	An array of groups assigned as Operators on the server.
name	A single Operator group.
viewer_role	
users	An array of users assigned as Viewers on the server.
name	A single Viewer user.
groups	An array of groups assigned as Viewers on the server.
name	A single Viewer group.
disable_inheritance	Set to "true" if you do not want the server to inherit ACLs from its ancestors (in addition to its explicit ACL). If set to "false" (this is also the default when it is not set), ACLs will be inherited from ancestors in addition to any explicit ACLs.

cURL Example

Request	<code>CURL.EXE -i -k -X PUT --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGr" -</code>
----------------	---

```
-header "Content-Length: 638"
https://computer.network.net/attunityenterprisemanager/
api/v1/servers/myreprsv1?action=acl" -T
"C:\myreprsv1Acl.json"
```

Request Body
(defined in
myreprsv1Acl.js
on)

```
{
  "admin_role": {
    "users": [
      {"name": "ATTUNITY\\Paul.Clarke"},
      {"name": "ATTUNITY\\testAuth1"}
    ],
    "groups": [
      {"name":
"ATTUNITY\\AttunityEnterpriseManagerAdmin
s"}
    ]
  },
  "designer_role": {
    "users": [
      {"name": "ATTUNITY\\Marisa.Lewis"},
      {"name": "ATTUNITY\\testAuth2"}
    ],
    "groups": [
      {"name":
"ATTUNITY\\AttunityEnterpriseManagerDesign
ers"}
    ]
  },
  "operator_role": {
    "users": [
      {"name": "ATTUNITY\\David.Foster"},
      {"name": "ATTUNITY\\testAuth3"}
    ],
    "groups": [
      {"name":
"ATTUNITY\\AttunityEnterpriseManagerOperat
ors"}
    ]
  },
  "viewer_role": {
    "users": [
      {"name": "ATTUNITY\\Laura.Todd"},
      {"name": "ATTUNITY\\testAuth4"}
    ],
    "groups": [
      {"name":
"ATTUNITY\\AttunityEnterpriseManagerViewe
rs"}
    ]
  }
}
```

```
    ],  
    },  
    "disable_inheritance": true  
  }  
}
```

Response

Header:

```
HTTP/1.1 200 OK  
Cache-Control: no-cache, no-store  
Content-Length: 38  
Content-Type: application/json; charset=utf-8  
Server: Microsoft-HTTPAPI/2.0  
Date: Mon, 26 Dec 2016 16:31:01 GMT
```

Error Response

All of the [general errors](#) as well as the errors listed in the table below.

HTTP Code	AEM Code	Text	Description
500	DESERIALIZE_TO_TYPE	"Failed to deserialize json to type AemAuthorizationAcl: {message}"	Returned when the JSON format is invalid format. For example, such an error will be returned if the JSON contains an unknown role.
500	AEM_PUT_SERVER_ACL_INNER_ERR	Failed to put ACL of server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to put the server's ACL.
500	AEM_NO_DOMAIN_IN_USER	User "{userName}" must be preceded by a domain name, separated by a backslash. Example: domain_name\user_name.	Returned when the domain is missing from the user name.
500	AEM_NO_DOMAIN_IN_GROUP	Group "{groupName}" must be preceded by a domain name, separated by a backslash. Example: domain_name\group_name.	Returned when the domain is missing from the group name.
500	AEM_NO_ADMIN_ON_SERVER	Requested server "{serverName}" has no admin user. At least one user or group must be assigned to the "admin" role.	Returned when there is no admin on the server. Possible reasons: <ul style="list-style-type: none"> » The request JSON is set to <code>disable_inheritance=true</code> and the explicit admin role in the JSON is empty. » The JSON is set to <code>disable_inheritance=true</code>, the explicit admin role in the

HTTP Code	AEM Code	Text	Description
			JSON is empty, and the parent levels do not have an admin user to inherit.
500	AEM_USER_ASSIGNED_TO_MULTIPLE_ROLES	User "{userName}" is assigned to multiple roles. Users can only be assigned to a single role.	Returned when a user is assigned to multiple roles.
500	AEM_GROUP_ASSIGNED_TO_MULTIPLE_ROLES	Group "{groupName}" is assigned to multiple roles. Groups can only be assigned to a single role.	Returned when a group is assigned to multiple roles.
500	AEM_USER_GROUP_MULTIPLE_ASSIGNED	"{userName/groupName}" is assigned to multiple roles or to the same role twice. Users/groups can only be assigned once, and to a single role.	Returned either when the specified user already exists as a group in the same/another role, or the specified group already exists as a user in the same/another role.

AemGetServer

General

Title	AemGetServer
URL	https://[host]/attunityenterprisemanager/api/v1/servers/[server]/def
Description	Retrieves the definition (Connection Properties) of the specified server. This method can be used together with <code>AemPutServer</code> in order to update the connection properties of an existing server. First call <code>AemGetServer</code> , then edit the returned properties as required, and finally, call <code>AemPutServer</code> .
HTTP Method	GET
Required User Role	Operator on server

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Response Body

```

Body      {
    "$type": "{string}",
    "name": "{string}",
    "description": "{string}",
    "host": "{string}",
    "port": "{string}",
    "username": "{string}",
    "password": "{string}",
    "monitored": "{bool}"
}

```

Response Parameters

Name	Description
\$type	The server's type. Can either be <code>AemReplicateServer</code> or <code>AemComposeServer</code> .
name	The name of the server.
description	The description of the server.
host	The host name or IP address of the server.
port	The port through which the server is accessed.
username	The user name to connect to the Replicate/Compose Server.
password	The password to connect to the Replicate/Compose Server.

Note The password identifier (GUID) that is returned by `AemGetServer` is valid only for the session in which it was generated. Using it in another session (for example as input for

Name	Description
monitored	<p><code>AemPutServer</code>) will result in exception.</p> <p>Whether to retrieve tasks and messages from this server or not.</p>

cURL Example

Request `CURL.EXE -i -k --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGr"
https://computer.network.net/attunityenterprisemanager/
api/v1/servers/myrepsrv1/def`

Response Headers:
HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 224
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 13:18:27 GMT

Payload:

```
{  
  "$type": "AemReplicateServer",  
  "name": "myrepsrv1",  
  "description": "replicate for business",  
  "host": "rep2018r2gs7.qa.int",  
  "port": "443",  
  "username": "administrator",  
  "password": "{S:98bdfd05-d16e-4afb-ad24-256c4dc6aae9}",  
  "monitored": true  
}
```

Error Response

All of the [general errors](#) as well as the following error:

HTTP Code	AEM Code	Text	Description
500	AEM_GET_SERVER_INNER_ERR	Failed to get server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to get the server details.

AemGetServerAcl

General

Title	AemGetServerAcl
URL	https://[host]/attunityenterprisemanager/api/v1/servers/[server]?action=acl
Description	<p>Retrieves the explicit ACL defined in AEM for the specified server, including a Boolean indication if ACL inheritance is disabled or enabled for the server.</p> <p>The method returns the explicit ACL only. In other words, it does not return inherited ACLs.</p> <p>If all of the servers ACLs are inherited (i.e. no ACL was explicitly defined for the server), an error will be returned indicating that no ACL was found.</p> <p>This method can be used together with <code>AemPutServerAcl</code> in order to update an existing server's ACL. First call <code>AemGetServerAcl</code>, then edit the returned roles as required, and finally, call <code>AemPutServerAcl</code>.</p>
HTTP Method	GET
Required User Role	Operator on the specified server

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myreprsv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Response Body

```
{
  "admin_role": {
    "users": [ { "name": "{string}" }, { "name": "{string}" }, ... ],
    "groups": [ { "name": "{string}" }, { "name": "{string}" }, ... ]
  },
  "designer_role": {
    "users": [ { "name": "{string}" }, { "name": "{string}" }, ... ],
    "groups": [ { "name": "{string}" }, { "name": "{string}" }, ... ]
  },
  "operator_role": {
    "users": [ { "name": "{string}" }, { "name": "{string}" }, ... ],
    "groups": [ { "name": "{string}" }, { "name": "{string}" }, ... ]
  },
  "viewer_role": {
    "users": [ { "name": "{string}" }, { "name": "{string}" }, ... ],
    "groups": [ { "name": "{string}" }, { "name": "{string}" }, ... ]
  },
  "disable_inheritance": "{bool}"
}
```

Response Parameters

Name	Description
admin_role	
users	An array of users assigned as Admins on the server.
name	A single Admin user.
groups	An array of groups assigned as Admins on the server.
name	A single Admin group.
designer_role	
users	An array of users assigned as Designers on the server.
name	A single Designer user.
groups	An array of groups assigned as Designers on the server.
name	A single Designer group.
operator_role	
users	An array of users assigned as Operators on the server.
name	A single Operator user.
groups	An array of groups assigned as Operators on the server.
name	A single Operator group.
viewer_role	
users	An array of users assigned as Viewers on the server.
name	A single Viewer user.
groups	An array of groups assigned as Viewers on the server.
name	A single Viewer group.
disable_inheritance	If set to "true", the server does not inherit ACLs from its ancestors (in addition to its explicit ACLs). If set to "false", the server inherits ACLs from its ancestors, in addition to any explicit ACLs.

cURL Example

Request `CURL.EXE -i -k --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGr" https://computer.network.net/attunityenterprisemanager/api/v1/servers/myrepsrv1?action=acl"`

Response Headers:

```
HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 502
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 13:18:27 GMT
```

Payload:

```
{
  "admin_role": {
    "users": [
      {"name": "ATTUNITY\\Paul.Clarke"},
      {"name": "ATTUNITY\\testAuth1"}
    ],
    "groups": [
      {"name":
        "ATTUNITY\\AttunityEnterpriseManagerAdmins"}
    ]
  },
  "designer_role": {
    "users": [
      {"name": "ATTUNITY\\Marisa.Lewis"},
      {"name": "ATTUNITY\\testAuth2"}
    ],
    "groups": [
      {"name":
        "ATTUNITY\\AttunityEnterpriseManagerDesigners"}
    ]
  },
  "operator_role": {
    "users": [
      {"name": "ATTUNITY\\David.Foster"},
      {"name": "ATTUNITY\\testAuth3"}
    ],
    "groups": [
      {"name":
        "ATTUNITY\\AttunityEnterpriseManagerOperators"}
    ]
  },
  "viewer_role": {
```

```

    "users": [
      {"name": "ATTUNITY\\Laura.Todd"},
      {"name": "ATTUNITY\\testAuth4"}
    ],
    "groups": [
      {"name":
        "ATTUNITY\\AttunityEnterpriseManagerViewers"}
    ]
  },
  "disable_inheritance": true
}

```

Error Response

All of the [general errors](#) as well as the errors listed in the table below.

HTTP Code	AEM Code	Text	Description
500	AEM_GET_SERVER_ACL_INNER_ERR	Failed to get ACL of server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to get the server ACL.
500	AEM_SERVER_HAS_NO_ACL	ACL for server "{server}" could not be found.	Returned if no explicit ACL is defined for the server.

Note A server that does not have its own explicit ACL inherits the ACL from its ancestors. Inherited ACLs are *not* returned by this method.

AemGetServerList

General

Title	AemGetServerList
URL	https://[host]/attunityenterprisemanager/api/v1/servers
Description	Retrieves a list of servers under AEM management as well as each server's properties . Required permission: Viewer access or above.
HTTP Method	GET
Required User Role	Viewer

Request Parameters

Location	Name	Required	Example
URL	host [string]	Yes	computer.network.net
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Response Body

```

Body
{
  "serverList": [{
    "$type": "{string}",
    "name": "{string}",
    "description": "{string}",
    "host": "{string}",
    "port": "{string}",
    "state": "{enum_server_state}",
    "message": "{string}",
    "platform": "{enum_server_platform}",
    "version": "{string}",
    "last_connection": "{string}"
  }, ...

```

```
    ]
  }
```

Response Parameters

Name	Description
\$type	The server's type, which can either be <code>ReplicateServerInfo</code> or <code>ComposeServerInfo</code> .
name	The name of the server.
description	The description of the server.
host	The host name or IP address of the server.
port	The port through which the server is accessed.
state	The current state of the server.
message	The error message if AEM fails to connect and monitor the server.
platform	The operating system on which the server is installed.
version	The version of the server.
last_connection	The date and time of the last successful sync/retrieval of tasks and messages.

cURL Example

Request `CURL.EXE -i -k --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGr https://computer.network.net/attunityenterprisemanager/api/v1/servers`

Response Headers:
 HTTP/1.1 200 OK
 Cache-Control: no-cache, no-store
 Content-Length: 1658
 Content-Type: application/json; charset=utf-8
 Server: Microsoft-HTTPAPI/2.0
 Date: Mon, 26 Dec 2016 13:18:27 GMT
 Payload:
 {

```
"serverList": [{
  "$type": "ReplicateServerInfo",
  "name": "RepBS",
  "description": "replicate for business",
  "host": "rep2008r2gs7.qa.int",
  "port": "443",
  "state": "MONITORED",
  "message": "",
  "platform": "WINDOWS",
  "version": "5.2.0.156",
  "last_connection": "2016-12-18T02:23:30",
}, {
  "$type": "ReplicateServerInfo",
  "name": "RepDev",
  "description": "replicate for developers",
  "host": "rep2008r2gs8.qa.int",
  "port": "443",
  "state": "NOT_MONITORED",
  "message": "Server changed status to Not
Monitored.",
  "platform": "WINDOWS",
  "version": "5.2.0.156",
  "last_connection": "2016-11-16T05:30:00",
}, {
  "$type": "ReplicateServerInfo",
  "name": "RepProd",
  "description": "replicate for production",
  "host": "rep2008r2gs9.qa.int",
  "port": "443",
  "state": "ERROR",
  "message": "REPLICATE-E-REPSRVNFND, Replicate
server 'Rep 5003' not found. Last Connection:
12:21 PM",
  "platform": "WINDOWS",
  "version": "5.2.0.156",
  "last_connection": "2016-11-16T05:30:00",
}
]
}
```

AemDeleteServer

General

Title	AemDeleteServer
URL	https://[host]/attunityenterprisemanager/api/v1/servers/[server]/def
Description	<p>When this method is called, AEM will:</p> <ul style="list-style-type: none"> » Delete the specified server from AEM » Stop monitoring any tasks that were defined on the server » Delete all messages related to the server from the Message Center » Delete all user roles defined for the server, the server tasks, and the server endpoints
	<div style="border: 1px solid #add8e6; border-radius: 10px; padding: 10px; background-color: #e0f2f7;"> <p>Note The above operations will be performed, regardless of whether the server is currently being monitored or in an error state.</p> </div>
	Note:
HTTP Method	DELETE
Required User Role	Admin on server

Request Parameters

Location	Name	Required	Example
URL	host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

cURL Example

Request	<pre>curl -i -k -X DELETE --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGrw" --header "Content-Length: 0" https://computer.network.net/attunityenterprisemanager/api/v1/ servers/myreprsv1/def</pre>
Response	<pre>Header: HTTP/1.1 200 OK Cache-Control: no-cache, no-store Content-Length: 38 Content-Type: application/json; charset=utf-8 Server: Microsoft-HTTPAPI/2.0 Date: Mon, 26 Dec 2016 16:31:01 GMT</pre>

Error Response

All of the [general errors](#) as well as the errors listed in the table below.

HTTP Code	AEM Code	Text	Description
500	AEM_SERVER_NOT_FOUND	Requested server "{server}" could not be found.	The server name is unknown to AEM.
500	AEM_DELETE_SERVER_INNER_ERR	Failed to delete requested server "{server}".	AEM encountered an error/exception when trying to delete the server.

AemDeleteServerAcl

General

Title	AemDeleteServerAcl
URL	https://[host]/attunityenterprisemanager/api/v1/servers/[server]?action=acl
Description	<p>Deletes the explicit ACL defined in AEM for the specified server.</p> <p>Inherited ACLs are not affected by this method.</p> <p>Once the explicit ACL is deleted from the server, all ACLs will</p>

	be automatically inherited from the server's ancestors.
HTTP Method	DELETE
Required User Role	Admin on the specified server.

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

cURL Example

Request `CURL.EXE -i -k -X DELETE --header "EnterpriseManager.APISessionID: wCo0_KvjEUFR0vfHF5KGr" --header https://computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1?action=acl"`

Response Header:

```

HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 38
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 16:31:01 GMT

```

Error Response

All of the [general errors](#) as well as the errors listed in the table below.

HTTP Code	AEM Code	Text	Description
500	AEM_DELETE_SERVER_ACL_INNER_ERR	Failed to delete ACL of server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to delete the server's ACL.
500	AEM_SERVER_HAS_NO_ACL	ACL for server "{server}" could not be found.	Returned when the specified server has no explicit ACL defined.

AemGetTaskList

General

Title	AemGetTaskList
URL	<code>https://{host}/attunityenterprisemanager/api/v1/servers/{ServerName}/tasks</code>
Description	Receive a list of tasks per selected and authorized server. For each task, the API returns a few parameters.

Method	GET
Required User Role	Viewer

Request Parameters

Location	Name	Required	Example
URL	host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myreprsv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_ KvjEUFROvfHF5KGrw

Response Body

```

Body {
  "taskList": [{
    "name": "{string}",
    "state": "{enum task_state}",
    "stop_reason": "{enum stop_reason}",
    "message": "{string}",
    "assigned_tags": ["string", "string", "string", ...]
  }, {
    "name": "{string}",
    "state": "{enum task_state}",
    "stop_reason": "{enum stop_reason }",
    "message": "{string}",
    "assigned_tags": ["string", "string", "string", ...]
  }, {
    "name": "{string}",
    "state": "{enum task_state}",
    "stop_reason": "{enum stop_reason}",
    "message": "{string}",
    "assigned_tags": ["string", "string", "string", ...]
  }
]
}

```


Response Parameters

Name	Description
name	The name of the task.
state	The current state of the task.
stop_reason	The reason the task has stopped.
message	The message if the task stopped due to an error.
assigned_tags	Returns the custom tags assigned to the task. If no tags are assigned to the task, an empty array will be returned.

cURL Example

Request `curl -i -k --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGrw" https://computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1/tasks`

Response Headers:

```
HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 205
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 11:18:53 GMT
```

Payload:

```
{
  "taskList": [{
    "name": "Task1",
    "state": "RUNNING",
    "stop_reason": "NONE",
    "message": "NONE",
    "assigned_tags": ["MyTag1", "MyTag2", "MyTag3"]
  }, {
    "name": " Task2",
    "state": "STOPPED",
    "stop_reason": "FULL_LOAD_ONLY_FINISHED",
    "message": "NONE",
    "assigned_tags": ["MyTag5"]
  }
}
```

```

    }, {
      "name": "Task3",
      "state": "RUNNING",
      "stop_reason": "NONE",
      "message": "NONE",
      "assigned_tags": []
    }
  ]
}

```

AemGetTaskDetails

General

Title	AemGetTaskDetails
URL	https://{host}/attunityenterprisemanager/api/v1/servers/{ServerName}/tasks/{TaskName}
Description	Retrieves details about a selected and authorized task. The API returns full monitoring information related to the selected task.
HTTP Method	GET
Required User Role	Viewer

Request Parameters

Location	Name	Required	Example
URL	host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myreprsv1
URL	TaskName [string]	Yes	SalesDBBackup
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Response Body

```

Body {
  "task":{
    "name":"{string}",
    "state":"{enum task_state}",
    "message": "{string}",
    "source_endpoint":{
      "name":"{string}",
      "type":"{string}",
    "target_endpoint":{
      "name":"{string}",
      "type":"{string}",
    "cdc_event_counters":
      {"applied_insert_count":"{int64}",
      "applied_update_count":"{int64}",
      "applied_delete_count":"{int64}",
      "applied_ddl_count":"{int64}"
    },{
    "full_load_counters":{
      "tables_completed_count":"{int64}",
      "tables_loading_count":"{int64}",
      "tables_queued_count":"{int64}",
      "tables_with_error_count":"{int64}",
      "records_completed_count":"{int64}",
      "estimated_records_for_all_tables_count":"{int64}",
    },{
      "full_load_completed":"{bool}",
      "full_load_start":"{string}",
      "full_load_end":"{string}",
    },{
    "full_load_throughput":{
      "cdc_throughput": {
        "source_throughput_records_count": {
          "current": "{int32}"
        },
      "source_throughput_volume": {
        "current": "{int32}"
      }
    }
  }
}

```

```

    },
    "target_throughput_records_count": {
      "current": "{int32}"
    },
    "target_throughput_volume": {
      "current": "{int32}"
    }
  },
  {
    "cdc_throughput":{
      "source_throughput_records_count":"{int32}",
      "source_throughput_volume":"{int32}",
      "target_throughput_records_count":"{int32}",
      "target_throughput_volume":"{int32}"
    },
    "cdc_transactions_counters":{
      "commit_change_records_count":"{int64}",
      "rollback_transaction_count":"{int64}",
      "rollback_change_records_count":"{int64}",
      "rollback_change_volume_mb":"{int64}",
      "applied_transactions_in_progress_count":"{int64}",
      "applied_records_in_progress_count":"{int64}",
      "applied_comitted_transaction_count":"{int64}",
      "applied_records_comitted_count":"{int64}",
      "applied_volume_comitted_mb":"{int64}",
      "incoming_accumulated_changes_in_memory_count":"{int64}",
      "incoming_accumulated_changes_on_disk_count":"{int64}",
      "incoming_applying_changes_in_memory_count":"{int64}",
      "incoming_applying_changes_on_disk_count":"{int64}",
    },
    "cdc_latency":{
      "source_latency":"{int32}",
      "total_latency":"{int32}",
    },
    "replicate_profile":"{enum replicate_profile}",
    "task_stop_reason":"{enum task_stop_reason}",
    "memory_mb":{int64},

```

```

    "cpu_percentage": "{int32}",
    "disk_usage_mb": "{int64}",
    "data_error_count": "{int64}",
    "options": {"full_load_enabled": "{bool}", "apply_changes_
enabled": "{bool}", "store_changes_enabled": "{bool}", "audit_
changes_enabled": "{bool}"},
    "log_stream_staging": "{string}",
    "assigned_tags": ["string", "string", "string", ...]
  }
}

```

Response Parameters

Name	Description
Name	The name of the task.
State	The current state of the task.
message	The message returned if the task stopped due to error.
source_endpoint	
name	The name of the source endpoint.
type	The source endpoint type.
target_endpoint	
name	The name of the target endpoint.
type	The target endpoint type.
cdc_event_counters	
applied_insert_count	The number of records added in total for all tables
applied_update_count	The number of records updated in total for all tables
applied_delete_count	The number of records deleted in total for all tables
applied_ddl_count	The total number of metadata changes, such as add column
full_load_counters	
tables_completed_count	The number of tables that have been loaded into the target endpoint
tables_loading count	The number of tables that are currently being loaded into the target endpoint

Name	Description
tables_queued_count	The number of tables that are waiting to be loaded due to an error
tables_with_error_count	The number of tables that could not be loaded due to an error
records_completed_count	The total number of records that have completed loading into the target endpoint
estimated_records_for_all_tables_count	The estimated number of records remaining to be loaded into the target endpoint
full_load_completed	Indicates whether the full load process has ended
full_load_start	The start time of the full load process Format: YYYY MM DD Timezone: UTC
full_load_throughput	Indicates how fast the table records are being replicated to the target endpoint (by number or volume of records)
source_throughput_records_count	The current source throughput, in rec/sec
source_throughput_volume	The current source throughput, in kbyte/sec
target_throughput_records_count	The current target throughput, in rec/sec
target_throughput_volume	The current target throughput, in kbyte/sec
cdc_throughput	Indicates how fast the table records are being replicated to the target endpoint (by number or volume of records). Refers only to the current/last CDC.
source_throughput_records_count	The current source throughput, in rec/sec
source_throughput_volume	The current source throughput, in kbyte/sec
target_throughput_records_count	The current target throughput, in rec/sec
target_throughput_volume	The current target throughput, in kbyte/sec
cdc_transaction_counters	All numeric data concerning CDC transactions
commit_change_records_count	The number of COMMIT change records
rollback_transaction_count	The number of ROLLBACK transactions
rollback_change_records_count	The number of ROLLBACK change records
rollback_change_volume_mb	The volume of ROLLBACK change, in MB

Name	Description
applied_transactions_in_progress_count	The number of transactions in progress
applied_records_in_progress_count	The sum of all records/events in all In-Progress transactions
applied_committed_transaction_count	The number of transactions committed
applied_records_committed_count	The sum of all records/events in all Completed transactions
applied_volume_committed_mb	The sum of all volume/events in all Completed transactions, in MB
incoming_accumulated_changes_in_memory_count	The number of changes accumulated in memory until source commit
incoming_accumulated_changes_on_disk_count	The number of changes accumulated on disk until source commit
incoming_applying_changes_in_memory_count	The number of changes in memory during apply and until target commit
incoming_applying_changes_on_disk_count	The number of changes on disk during apply and until target commit
cdc_latency	CDC latency information
source_latency	The time gap between the original change in the source endpoint and capturing it, in hh:mm:ss
total_latency	The overall latency (source latency + target latency + apply latency), in hh:mm:ss
replicate_profile	The replication type between endpoints.
task_stop_reason	The reason the task stopped
memory_mb	The current utilization of memory, in MB. A task's memory utilization is sampled every 10 seconds. When the task is not running, the value is set to zero (0).
cpu_percentage	The current CPU usage of the Replicate task process.

Notes

Only available for Replicate tasks running on Replicate 6.2

Name	Description
<p>and above. When not available, this parameter will be returned as -1.</p>	
disk_usage_mb	The current utilization of disk space, in MB. A task's disk utilization is sampled every minute.
data_error_count	The total number of data errors in all tables involved in the task. The count is affected by data errors and the Reset Data Errors option available when you drill down to a task.
full_load_enabled	See Task Options .
apply_changes_enabled	See Task Options .
store_changes_enabled	See Task Options .
audit_changes_enabled	See Task Options .
log_stream_staging	If the task is writing to/reading from the Log Stream staging folder, the name of the associated Log Stream Staging task will be returned. Otherwise, an empty string will be returned.
assigned_tags	Returns the custom tags assigned to the task. If no tags are assigned to the task, an empty array will be returned.

cURL Example

Request `CURL.EXE -i -k --header "EnterpriseManager.APISessionID: {SessionID}" https://{host}/attunityservices/api/v1/servers/myrepsrv1/tasks/SalesDBBackup`

Response Headers:

```

HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 1658
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 13:18:27 GMT
Payload:
{
  "task":{
    "name":"SalesDBBackup",
    "state":"RUNNING",
    "message":"NONE",
    "source_endpoint":{
      "name":"Customer Management",
      "type":"Oracle",
    },
    "target_endpoint":{
      "name":"Business Management",
      "type":"Microsoft SQL Server",
    },
  },
  "cdc_event_counters":
  {"applied_insert_count":0,
   "applied_update_count":0,
   "applied_delete_count":0,
   "applied_ddl_count":0
  },
  "full_load_counters":{
    "tables_completed_count":3,
    "tables_loading_count":0,
    "tables_queued_count":0,
    "tables_with_error_count":0,
    "records_completed_count":177446,
  }
}
```

```

    "estimated_records_for_all_tables_count":177446,
    "full_load_completed":true,
    "full_load_start":"2016-12-18T02:23:30",
    "full_load_end":"2016-12-18T02:23:35",
  },{
    "full_load_throughput":{
      "source_throughput_records_count":0,
      "source_throughput_volume":0,
      "target_throughput_records_count":0,
      "target_throughput_volume":0},
  },{
    "cdc_throughput":{
      "source_throughput_records_count": {
        "current": 0
      },
      "source_throughput_volume": {
        "current": 0
      },
      "target_throughput_records_count": {
        "current": 0
      },
      "target_throughput_volume": {
        "current": 0
      }
    },{
      "cdc_transactions_counters":{
        "commit_change_records_count":0,
        "rollback_transaction_count":0,
        "rollback_change_records_count":0,
        "rollback_change_volume_mb":0,
        "applied_transactions_in_progress_count":0,
        "applied_records_in_progress_count":0,
        "applied_comitted_transacion_count":0,
        "applied_records_comitted_count":0,
        "applied_volume_comitted_mb":0,
        "incoming_accumulated_changes_in_memory_count":0,
        "incoming_accumulated_changes_on_disk_count":0,

```

```

    "incoming_applying_changes_in_memory_count":0,
    "incoming_applying_changes_on_disk_count":0},
  },{
  "cdc_latency":{
    "source_latency":"00:00:00",
    "total_latency":"00:00:00"},
  },{
  "replicate_profile":"UNIDIRECTIONAL",
  "task_stop_reason":"NORMAL",
  "memory_mb":57,
  "cpu_percentage":30,
  "disk_usage_mb":0,
  "data_error_count":0,
  "options":{"full_load_enabled":true,"apply_changes_
enabled":true,"store_changes_enabled":false,"audit_changes_
enabled":false},
  "log_stream_staging":"MyLogStreamTask",
  "assigned_tags": ["MyTag1", "MyTag2", "MyTag3"]
}
}

```

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_TASK_NOT_FOUND	Replicate task {task} on server {server} could not be found.	The task name is unknown to AEM.

AemDeleteTask

General

Title	AemDeleteTask
URL	https[host]/attunityenterprisemanager/api/v1/servers/[server]/tasks/[task]?action=delete&deletetasklogs=[deletetasklogs]
Description	Deletes the specified task. The task's logs will be deleted only if <code>deletetasklogs=true</code> is specified in the URL.

HTTP Method	POST
Required User Role	Designer

Request Parameters

Location	Name	Required	Example
URL	host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
URL	TaskName [string]	Yes	SalesDBBackup
URL	deletetasklogs [bool]	Optional (default is false)	deletetasklogs=true
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw
Header	Content-Length:	Yes	"Content-Length: 0" Note: The specified value must be "0".

cURL Example

Request `curl -i -k -X POST --header "EnterpriseManager.APISessionID:wCo0_KvjEUFROvfHF5KGrw" --header "Content-Length: 0" https:// computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1/tasks/SalesDBBackup?action=delete&deletetasklogs=true`

Response Header:

```

HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 38
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 16:31:01 GMT

```

Error response

HTTP Code	AEM Code	Text	Description
500	AEM_TASK_NOT_FOUND	Replication task {task} on server {server} could not be found.	Returned if the task name is unknown to AEM.
500	AEM_DELETE_TASK_INNER_ERR	Replication task {task} on server {server} could not be deleted due to an error.	Returned if AEM encounters an error/exception when trying to delete the task.
500	AEM_DELETE_TASK_ERR	Replication task {task} on server {server} could not be deleted due to an error. {2}	Returned if AEM encounters an error when trying to delete the task.
500	AEM_TASK_NOT_STOPPED	Replication task {task} on server {server} must be stopped before it can be deleted.	Returned if the replication task was running when <code>AemDeleteTask</code> attempted to delete it.

AemExportTask

General

Title	AemExportTask
URL	https://{Host}/attunityenterprisemanager/api/v1/servers/{ServerName}/tasks/{TaskName}?action=export&withendpoints={withendpoints}
Description	Export definitions from the selected task on the selected server. The definitions always include task settings, tables/table patterns (include/exclude), table settings and global transformations. The endpoint definition is only exported along with the task definition if withendpoints=true is specified in the URL. Supported only from Replicate 5.2 and later.
HTTP Method	GET
Required User Role	Operator

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
URL	TaskName [string]	Yes	SalesDBBackup
URL	withendpoints [bool]	Yes	true/false
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Response

JSON File (stream)

cURL Example

Request `CURL.EXE -i -k --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGrw" https://computer.network.net/attunityenterprisemanager/api/v1/servers/myrepsrv1/tasks/SalesDBBackup?action=export&withendpoints=true`

Response JSON file (stream)

Error Response

HTTP Code	AEM Code	Text	Description
500		AemExportTask is only supported on Replicate 5.2 or above.	
500	AEM_EXPORT_TASK_NO_PERMISSION_ON_ENDPOINT	Failed to export task {task} from Replicate server {server} as the logged in user does not have permission to access one or both of the task's endpoints.	Export all cannot be carried out because the user does not have permissions on one or more endpoints.

AemImportTask

General

Title	AemImportTask
URL	<code>https://{Host}/attunityenterprisemanager/api/v1/servers/{ServerName}/tasks/{task}?action=import</code>
Description	<p>Import a single task's JSON definitions provided in the request body into the requested server repository on the selected server.</p> <p>The ImportTask method enables importing all valid JSON definitions provided in the request body. This includes task settings, tables/table patterns (include/exclude), table settings and global transformations. Information about endpoints is included if it was included in the JSON file.</p> <p>When you import a task, Items that existed in the target server before the</p>

import and have no new JSON definition in the request body are not modified and not removed. This means that ImportTask provides no way of removing old definitions that are no longer needed.

Supported only with Replicate 5.2 and later.

HTTP Method	POST
Required User Role	Designer on relevant task If endpoint definitions are included in the JSON definition, a user must also be Designer on the relevant endpoints

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myreprsv1
URL	TaskName [string]	Yes	SalesDBBackup
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw
Header	Content-Length: This is the number of bytes in the content body. Note that the number of bytes that you specify must be exactly the same as the number of bytes in the JSON file. This number can be ascertained by copy-pasting the text into a text editor such as Notepad ++ (which shows the number of bytes as "Length" at the bottom of its console).	Yes	"Content-Length: 3986"
Body	A JSON document to import [stream]	Yes	localServer1.json

Response

JSON File

cURL Example

```
cURL Example  CURL.EXE -i -k -X POST --header "EnterpriseManager.APISessionID:
wCo0_KvjEUFROvfHF5KGrw " --header "Content-Length: 3986" --
header "Content-Type: application/json" "
https://computer.network.net/attunityenterprisemanager/api/v1/se
rvers/ myreprsv1/tasks/SalesDBBackup?action=import" -T
"C:\exports\ SalesDBBackup.json"
```

```
Response  HTTP/1.1 100 Continue
HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 0
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Tue, 28 Feb 2017 17:45:41 GMT
```

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_IMPORT_TASK_NO_PERMISSION_ON_ENDPOINT	Failed to import task {task} to replication server {server} as the logged in user does not have permission to add or modify endpoints.	The task cannot be imported because it includes endpoint definitions, and the user does not have permissions to insert endpoints.
500	AEM_IMPORT_TASK_CONTAIN_ALIEN_ITEMS	Failed to import task {task} to replication server {server} as the JSON file contains unsupported objects.	The task cannot be imported because the stream contains items that cannot be imported (such as remote machines).
500	AEM_IMPORT_TASK_NAME_DIFFER	Failed to import task {task} to replication server {server} as the JSON file contains conflicting tasks.	The task cannot be imported because the stream contains conflicting tasks.
500	AEM_IMPORT_TASK_CONTAINS_MULTIPLE_	Failed to import task to replication server {server} as the JSON file contains multiple tasks. To import multiple tasks, use AemImportAll instead.	The task cannot be imported since the stream contains multiple tasks, and the method can only import a single task.

HTTP Code	AEM Code	Text	Description
TASKS			
500	AEM_TASK_NOT_IMPORTABLE	Failed to import task {task} as the task is running on server {server}. Stop the task and then try again.	Occurs when trying to import a running task.
500	AEM_IMPORT_TASK_CONTENT_EMPTY	Failed to import task {task} to replication server {server} as the JSON file is empty.	The task cannot be imported as the specified JSON file is empty.
500	AEM_IMPORT_TASK_ENDPOINT_DIFFER	Failed to import task {task} to server {server} as the endpoint names in the JSON file's "task" and "databases" sections are not the same.	The task cannot be imported as the endpoint names in the specified JSON file's "task" and "databases" sections are different.
500	AEM_IMPORT_TASK_NO_ENDPOINT_IN_SERVER	Failed to import task {task} to replication server {server} as the {role} endpoint {endpoint} does not exist on the target server.	The task cannot be imported as one of the endpoints specified in the exported JSON file does not exist on the target server.

AemStopTask

General

Title	AemStopTask
URL	https://{host}/attunityenterprisemanager/api/v1/servers/{ServerName}/tasks/{TaskName}?action=stop&timeout={timeout}
Description	Stop the selected task
HTTP Method	POST
Required User Role	Operator

Request Parameters

Location	Name	Required	Example
URL	<code>host</code> [string]	Yes	computer.network.net
URL	<code>ServerName</code> [string]	Yes	myreprsv1
URL	<code>TaskName</code> [string]	Yes	SalesDBBackup
URL	<code>Timeout</code> [int32]	Optional (default is 60 seconds)	60 (seconds)
Header	<code>EnterpriseManager.APISessionID</code> [string]	Yes	wCo0_KvjEUFROvfHF5KGrw
Header	<code>Content-Length</code>	Yes	Content-Length: 0 Note that the Content-Length value must be "0".

Response Body

```

Body
{
  "state": "{enum task_state}",
  "error_message": ""
}

```

Response Parameters

Name	Description
<code>state</code> [enum task_state]	The current state of the task
<code>error_message</code>	The description of the error

cURL Example

```

Request curl -i -k -X POST --header "EnterpriseManager.APISessionID:
wCo0_KvjEUFROvfHF5KGrw" --header "Content-Length: 0" https://
computer.network.net/attunityenterprisemanager/api/
v1/servers/myreprsv1/tasks/SalesDBBackup/
?action=stop

```

Response Header:

```

HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 38
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 16:31:01 GMT
Payload:
{
  "state": "STOPPED",
  "error_message": ""
}

```

Error response

HTTP Code	AEM Code	Text	Description
500	AEM_TASK_ALREADY_STOPPED	Replicate task {task} on server {server} is already stopped.	Cannot stop a task that is in Stopped state.
500	AEM_STOP_TASK_INNER_ERR	Failed to stop Replicate task {0} on server {1}: <{2}>	An error occurred while trying to stop the task.
500	AEM_STOP_TASK_TIMEOUT	A timeout occurred when trying to stop Replicate task {0} on server {1}	A timeout occurred while trying to stop the task.

AemRunTask

General

Title	AemRunTask
URL	https://{host}/attunityenterprisemanager/api/v1/servers/{ServerName}/tasks/{TaskName}?action=run&option={option}&timeout={timeout}
Description	Run the selected task according to the specified option.
HTTP	POST

Method

Required User Role Operator

Request Parameters

Location	Name	Required	Example
URL	host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myreprsv1
URL	TaskName [string]	Yes	SalesDBBackup
URL	Timeout [int32]	Optional (default is 60 seconds)	60 (seconds)
URL	option [enum run_options]	Yes	RELOAD_TARGET
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw
Header	Content-Type: [Type]	Yes if the run option = RESUME_PROCESSING_FROM_TIMESTAMP or RECOVER_USING_CHECKPOINT_STORED_ON_TARGET	"Content-Type: application/json" You can either specify the <code>Content-Type</code> payload inline or by referencing a JSON file. The payload format differs slightly according to whether it is specified inline or by referencing a JSON file. For more information, see Body below.
Header	Content-Length: This is the number of bytes in the content body. Note that the number of bytes that you specify must be exactly the same as the number of bytes in the JSON file. This number can be ascertained by copy-pasting the text	Yes if the option = RESUME_PROCESSING_FROM_TIMESTAMP or RECOVER_USING_	"Content-Length: 37" For example commands, see cURL Resume Processing from Timestamp Examples .

Location	Name	Required	Example
	into a text editor such as Notepad ++ (which shows the number of bytes as "Length" at the bottom of its console).	CHECKPOINT_ STORED_ON_ TARGET	
Body	cdcposition	Yes if the option = RESUME_ PROCESSING_ FROM_ TIMESTAMP or RECOVER_ USING_ CHECKPOINT_ STORED_ON_ TARGET	The <code>cdcposition</code> parameter can either be specified inline or in an external JSON file. The format for both is described in Request Body Format below.

Request Body Format

If the task **option** is RESUME_PROCESSING_FROM_TIMESTAMP, then the format should be:

JSON File Format:

```
{"cdcposition": "timestamp"}
```

Example:

```
{"cdcposition": "2017-03-07T11:19:03"}
```

Inline Format:

```
"{\\"cdcposition\\" : \\"timestamp\\"}"
```

Example:

```
"{\\"cdcposition\\" : \\"2017-03-07T11:19:03\\"}"
```

For example commands, see [cURL Resume Processing from Timestamp Examples](#).

If the task **option** is RECOVER_USING_CHECKPOINT_STORED_ON_TARGET, then the format should be:

JSON File Format:

```
{"cdcposition": "target_checkpoint"}
```

Example:

```
{"cdcposition":"Checkpoint:V1#1#timestamp:2017-02-14T12:34:44#0#0#*#0#0"}
```

Inline Format:

```
"{"cdcposition\":"target_checkpoint\"}"
```

Example:

```
"{"cdcposition\":"Checkpoint:V1#1#timestamp:2017-02-14T12:34:44#0#0#*#0#0\"}"
```

Response Body

```
Body      {
              "state":"{enum task_state}",
              "error_message":""
            }
```

Response Parameters

Name	Description
state {enum task_state}	The current state of the task
error_message	The description of the error

cURL Reload Target Example

```
cURL      curl -i -k -X POST --header "EnterpriseManager.APISessionID:wCo0_KvjEUFR0vfHF5KGrw" --header "Content-Length: 0" https://computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1/tasks/SalesDBBackup?action=run&option=RELOAD_TARGET
```

```
Response  Headers:
           HTTP/1.1 200 OK
           Cache-Control: no-cache, no-store
           Content-Length: 38
           Content-Type: application/json; charset=utf-8
           Server: Microsoft-HTTPAPI/2.0
           Date: Mon, 26 Dec 2016 16:28:25 GMT
```

```
Payload:
{
  "state": "RUNNING",
  "error_message": ""
}
```

cURL Resume Processing from Timestamp Examples

cURL When the payload content is in a JSON file:

```
curl -i -k -X POST --header "EnterpriseManager.APISessionID:wCo0_KvjEUFROvfHF5KGrw" --header "Content-Type: application/json" -T @"C:\exports\run.json" --header "Content-Length: 37" https://computer.network.net/attunityenterprisemanager/api/v1/servers/rep2008r2gs7.qa.int/tasks/SalesDBBackup?action=run&option=RESUME_PROCESSING_FROM_TIMESTAMP"
```

cURL When the payload content is inline.

```
curl -i -k -X POST --header "EnterpriseManager.APISessionID:wCo0_KvjEUFROvfHF5KGrw" --header "Content-Length: 0" -d '{"cdcposition": "2017-03-07T11:19:03"}' https://computer.network.net/attunityenterprisemanager/api/v1/servers/rep2008r2gs7.qa.int/tasks/SalesDBBackup?action=run&option=RESUME_PROCESSING_FROM_TIMESTAMP"
```

Response Headers:

```
HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 38
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Tue, 07 Mar 2017 16:57:27 GMT
```

Payload:

```
{"state": "RUNNING", "error_message": ""}
{"error_code": "INVALID_SESSION_ID", "error_message": "Session expired or invalid"}
```

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_TASK_	Replicate task {task} on server	The task cannot be run because

HTTP Code	AEM Code	Text	Description
	ALREADY_RUNNING	{server} is already running.	it is already running.
500	AEM_TASK_IN_RECOVERY	Replicate task {task} on server {server} cannot be run as it is in a recovery state.	The task cannot be run because it is in Recovery state.
500	AEM_WRONG_OPTION_FOR_CDCPOSITION	Replicate task {task} on server {server} cannot be run with cdcposition {position} and option {option}. Change the option to RESUME_PROCESSING_FROM_TIMESTAMP or RECOVER_USING_CHECKPOINT_STORED_ON_TARGET.	When the option Tables are already loaded. Start processing changes from Timestamp is selected in the Advanced Run Options dialog box for a task, the option sent to the API must be RESUME_PROCESSING_FROM_TIMESTAMP.
500	AEM_CDC_POSITION_ERR_FORMAT	The cdcposition parameter value for Replicate task {task} on server {server} is not in the correct format ('YYYY-MM-DDThh:mm:ssZ').	The cdcPosition parameter must follow this format: YYYY-MM-DDThh:mm:ssZ Parameters: task name and server name
500	AEM_RUN_TASK_TIMEOUT	Replicate task {task} on server {server} timed out when requested to "Run".	The task does not assume a Running state or any other steady state (error o stopped).
500	AEM_RUN_TASK_INNER_ERR	Replicate task {task} on server {server} encountered an error when requested to run.	Replicate experienced an error/exception when trying to run the task.
500	AEM_RUN_TASK_NO_SRC_NO_TRG	Replicate task {task} on server {server} has no source or target endpoints.	Task validation revealed that the task is missing a source and a target.
500	AEM_RUN_TASK_NO_SRC	Replicate task {task} on server {server} has no source endpoint.	Task validation revealed that the task is missing a source.
500	AEM_RUN_TASK_TRG	Replicate task {task} on server {server} has no target endpoint.	Task validation revealed that the task is missing a target endpoint.
500	AEM_RUN_TASK_NOT_FL_NOR_CDC	Replicate task {task} on server {server} cannot be run without at least one of the replication	Task validation of a unidirectional task revealed that the replication option definition

HTTP Code	AEM Code	Text	Description
		options enabled (Full Load, Apply Changes, or Store Changes).	for the task is missing (Full Load, Apply Changes, or Store Changes).
500	AEM_RUN_BIDI_TASK_NO_FL_NOR_CDC	Replicate task {task} on server {server} cannot be run without at least one of the replication options enabled (Full Load or Apply Changes).	Task validation of a unidirectional task revealed that the replication option definition for the task is missing (Full Load, Apply Changes, or Store Changes).

AemGetEndpointList

General

Title	AemGetEndpointList
URL	https://[host]/attunityenterprisemanager/api/v1/servers/[server]/endpoints
Description	Retrieves a list of endpoints and their properties for the specified server.
Method	GET
Required User Role	Viewer

Request Parameters

Location	Name	Required	Example
URL	host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myreprsv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Response Body

```

Body      {
    "endpointList": [{
        "name": "{string}",
        "description": "{string}",
        "role": "{enum endpoint_role}",
        "type": "{string}",
        "is_licensed": "{bool}"
    }, ...
    ]
}

```

Response Parameters

Name	Description
name	The endpoint name.
description	The endpoint description.
role	The endpoint role: SOURCE or TARGET
type	The endpoint type - for example, Oracle.
is_licensed	Indicates whether the endpoint is licensed on this server.

cURL Example

Request `curl -i -k --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGrw" https://computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1/endpoints`

Response Headers:

```

HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 205
Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Mon, 26 Dec 2016 11:18:53 GMT

```

Payload:

```

{

```

```

"endpointList": [{
  "name": "Shopping",
  "description": "Customers and purchases",
  "role": "SOURCE"
  "type": "ORACLE"
  "is_licensed": true
}, {
  "name": "Management",
  "description": "Managers and Employees",
  "role": "SOURCE"
  "type": "ORACLE"
  "is_licensed": true
}, {
  "name": "Business Management",
  "description": "Shopping + Management",
  "role": "TARGET"
  "type": "HADOOP"
  "is_licensed": true
}
]
}

```

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_ENDPOINT_LIST_INNER_ERR	Failed to retrieve endpoints list from Replicate server {name}.	Replicate experienced an error/exception when trying to retrieve the endpoint list.
403	See Error Handling .		
440	See Error Handling .		

AemDeleteEndpoint

General

Title	AemDeleteEndpoint
URL	https://[host]/attunityenterprisemanager/api/v1/servers/[server]/endpoints/[endpoint]?action=delete
Description	Deletes the specified endpoint. Note than an endpoint can only be deleted if it is not in use by any task.
HTTP Method	DELETE
Required User Role	Designer

Request Parameters

Location	Name	Required	Example
URL	host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
URL	EndpointName [string]	Yes	Shopping
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw
Header	Content-Length	Yes	Content-Length: 0 Note that the Content-Length value must be "0".

cURL Example

Request `curl -i -k -X POST --header "EnterpriseManager.APISessionID:wCo0_KvjEUFROvfHF5KGrw" --header "Content-Length: 0" https://computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1/endpoints/Shopping?action=delete`

Response Header:
 HTTP/1.1 200 OK
 Cache-Control: no-cache, no-store
 Content-Length: 38
 Content-Type: application/json; charset=utf-8
 Server: Microsoft-HTTPAPI/2.0
 Date: Mon, 26 Dec 2016 16:31:01 GMT

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_ENDPOINT_NOT_FOUND	Replicate endpoint {endpoint} on server {server} could not be found.	Endpoint name unknown to AEM.
500	AEM_DELETE_ENDPOINT_INNER_ERR	Failed to delete Replicate endpoint {endpoint} from server {server}.	Replicate encountered an error/exception when trying to delete the endpoint.
500	AEM_ENDPOINT_IS_IN_USE	Replicate endpoint {endpoint} on server {server} cannot be deleted as it is currently in use by one or more tasks.	The Replicate endpoint must be removed from its associated tasks before it can be deleted.
403	See Error Handling .		
440	See Error Handling .		

AemExportAll

General

Title AemExportAll

URL	https://{host}/attunityenterprisemanager/api/v1/servers/{ServerName}?action=export
Description	Export all definitions from the requested server repository on the selected server (server settings, tasks, endpoints, and so on). The definitions are exported to a JSON file. Supported only with Replicate 5.2 and later.
HTTP Method	GET
Required User Role	<ul style="list-style-type: none"> » AEM: Admin » Server: Admin » All Tasks: Designer » All Endpoints: Operator

Request Parameters

Location	URL Param Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myreprsv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Response

JSON File

cURL Example

Request	<pre>CURL.EXE -i -k --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGrw" https://computer.network.net/attunityenterprisemanager/api/v1/servers/myreprsv1?action=export</pre>
Response	JSON file (stream)

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_METHOD_NOT_SUPPORTED_VERSION	AemExportAll is only supported on Replicate 5.2 or above.	The method requires Replicate 5.2 or above.
500	AEM_EXPORT_NO_PERMISSION_ON_TASK	Failed to export all tasks from Replicate server {server} as the logged in user does not have permission to export one or more of the defined tasks.	Export all cannot be carried out because the user does not have permissions on one or more tasks.
500	AEM_EXPORT_NO_PERMISSION_ON_ENDPOINT	Failed to export all tasks from server {server} as the logged in user does not have permission to export one or more of the defined endpoints.	Export all cannot be carried out because the user does not have permissions on one or more endpoints.

AemImportAll

General

Title	AemImportAll
URL	https://{Host}/attunityenterprisemanager/api/v1/servers/{ServerName}?action=import
Description	<p>Import the JSON definitions provided in the request body into the requested server repository on the selected server.</p> <p>Supported only with replicate 5.2 and later.</p> <p>The ApiImportAll method uses "merge" semantics. In particular:</p> <ul style="list-style-type: none"> » All valid JSON definitions provided in the request body will be imported. This includes server settings, task settings, endpoints, and other definitions. » Items that existed in the target server before the import and have no new JSON definition in the request body will not be modified and in particular will not be removed. This means that ApiImportAll provides no way of removing old definitions that are no longer needed.

HTTP Method	POST
Required User Role	<ul style="list-style-type: none"> » AEM: Admin » Server: Admin » All Tasks: Designer » All Endpoints: Designer

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myreprsv1
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw
Header	Content-Length: This is the number of bytes in the content body. Note that the number of bytes that you specify must be exactly the same as the number of bytes in the JSON file. This number can be ascertained by copy-pasting the text into a text editor such as Notepad ++ (which shows the number of bytes as "Length" at the bottom of its console).	Yes	"Content-Length: 110952"
Body	A JSON document to import [stream]	Yes	localServer1.json

Response

JSON File (stream)

cURL Example

cURL Example `CURL.EXE -i -k -X POST --header "EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGrw" --header "Content-Length: 110952" --header`

"Content-Type: application/json" "
 https://computer.network.net/attunityenterprisemanager/api/v1/servers/
 myreprsv1?action=import" -T "C:\exports\localServer1.json"

Response HTTP/1.1 100 Continue
 HTTP/1.1 200 OK
 Cache-Control: no-cache, no-store
 Content-Length: 0
 Content-Type: application/json; charset=utf-8
 Server: Microsoft-HTTPAPI/2.0
 Date: Tue, 28 Feb 2017 19:05:12 GMT

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_METHOD_NOT_SUPPORTED_VERSION	AemImportAll is only supported on Replicate 5.2 or above.	The method requires Replicate 5.2 or above.
500	AEM_IMPORT_NO_PERMISSION_ON_TASK	Failed to import all tasks to replication server {server} as the logged in user does not have permission to add tasks.	Stream cannot be imported because the user does not have the permissions to add tasks.
500	AEM_IMPORT_NO_PERMISSION_ON_ENDPOINT	Failed to import all tasks to replication server {server} as the logged in user does not have permission to add endpoints.	Stream cannot be imported because the user does not have the permissions to add endpoints
500	AEM_IMPORT_CONTENT_EMPTY	Failed to import all tasks to replication server {server} as the JSON file is empty.	Stream cannot be imported because it contains no content.
500	AEM_IMPORT_INVALID_CONTENT	Failed to import all tasks to replication server {server} as the JSON file contains invalid content.	Stream cannot be imported because it contains invalid content.

AemReloadTable

General

Title	AemReloadTable
URL	https://{host}/attunityenterprisemanager/api/v1/servers/{server}/tasks/{task}/tables?action=reload&schema={schema}&table={table}
Description	Reload a specific table.
HTTP Method	POST
Required User Role	Operator

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myrepsrv1
URL	TaskName [string]	Yes	SalesDBBackup
URL	Schema [string]	Yes	dbo
URL	Table [string]	Yes	employeeelist
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw
Header	Content-Length	Yes	Content-Length: 0 Note: The specified value must be "0".

cURL Example

```
cURL Example  CURL.EXE -i -k -X POST --header "EnterpriseManager.APISessionID:
wCo0_KvjEUFROvfHF5KGrw" --header "Content-Length: 0"
"https://computer.network.net/attunityenterprisemanager/api/v1/s
ervers/
myrepsrv1/tasks/SalesDBBackup/tables?action=reload&schema=dbo&ta
ble= employeeelist"
```

Response HTTP/1.1 200 OK
 Cache-Control: no-cache, no-store
 Content-Length: 0
 Content-Type: application/json; charset=utf-8
 Server: Microsoft-HTTPAPI/2.0
 Date: Tue, 24 Jan 2017 13:34:38 GMT

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_INVALID_TASK_NOT_FL	Failed to reload table {table} as Full Load is not enabled for task {task}.	The table could not be reloaded because the task's Full Load replication option is not enabled.
500	AEM_INVALID_TASK_NT_NTSUPPEP	Failed to reload table as this operation is not supported with the File Channel source endpoint.	The table could not be reloaded because the task's source endpoint is File Channel.
500	AEM_RELOAD_TABLE_ERR	Failed to reload table {schema}. {table} for replication task {task} on server {server}: {message}	An error was encountered while trying to reload the specified table.

AemTestEndpoint

General

Title	AemTestEndpoint
URL	https://{host}/attunityenterprisemanager/api/v1/servers/{server} endpoints/{endpoint}?action=test&timeout={timeout}
Description	Contact an endpoint to test connectivity and configuration (permissions, CDC configuration).
HTTP Method	GET
Required User Role	Operator

Request Parameters

Location	Name	Required	Example
URL	Host [string]	Yes	computer.network.net
URL	ServerName [string]	Yes	myreprsv1
URL	EndpointName [string]	Yes	TargetSQL1
URL	Timeout [int32]	Optional (default is 60 sec)	60 (seconds)
Header	EnterpriseManager.APISessionID [string]	Yes	wCo0_KvjEUFROvfHF5KGrw

Response Body

```

Body
{
  "requeststate": "{enum requeststate_state}",
  "message": ""
  "detailed_message": ""
}

```

Response Parameters

Name	Description
state {enum endpoint_state}	The current state of the endpoint
message	Short description of the error
detailed message	Elaborate description of the error

cURL Example

```

cURL Example c:\Tools\curl>CURL.EXE -i -k --header
"EnterpriseManager.APISessionID: wCo0_KvjEUFROvfHF5KGrw"
"https://computer.network.net
/attunityenterprisemanager/api/v1/servers/
myreprsv1/endpoints/TargetSQL1c?action=test&timeout=60"

```

```

Response HTTP/1.1 200 OK
Cache-Control: no-cache, no-store
Content-Length: 61

```

```

Content-Type: application/json; charset=utf-8
Server: Microsoft-HTTPAPI/2.0
Date: Sun, 19 Feb 2017 16:42:11 GMT
Payload:
{
  "state": "CONNECTED",
  "error_message": ""
}

```

Error Response

HTTP Code	AEM Code	Text	Description
500	AEM_TEST_ENDPOINT_CONNECTION_TIMEOUT	A timeout occurred while testing the connection for endpoint {endpoint} on Replicate server {server}.	Connection was not established within 60 seconds.
500	AEM_ENDPOINT_NOT_FOUND	Replicate endpoint {0} on server {1} could not be found.	The specified endpoint could not be found.

Parameters

The following table lists all enum parameters used in the response body, along with their values.

Parameter Name	Value	Description
Server State	MONITORED	The server is being monitored, the AEM is connected and synchronized successfully.
	ERROR	AEM fails to connect and monitor the server.
	NOT_MONITORED	The server is not being monitored.
Server Platform	» WINDOWS	
	» LINUX	
License State	» LICENSE_VALID	

Parameter Name	Value	Description
	<ul style="list-style-type: none"> » LICENSE_INVALID_CHECKSUM » LICENSE_EXPIRED NO_LICENSE » MACHINE_NOT_LICENSED » INVALID_LICENSE 	
Endpoint Role	SOURCE or TARGET	Specifies whether an endpoint is being used as a source or a target in a Replicate task.
Task State	RUNNING	The task is running.
	STOPPED	The task has not been run yet or has stopped running at some point during the replication.
	ERROR	The task has stopped due to a fatal error.
	RECOVERING	The task has detected an error and is trying to recover. After a limited number of attempts, the task either recovers and the state returns to RUNNING, or the task fails and the state turns to ERROR.
Task options	full_load_enabled [bool]	Creates all files or tables at the target endpoint, automatically defines the metadata that is required at the target, and populates the tables with data from the source.
	apply_changes_enabled [bool]	Updates all changes made to files and tables that were created during the full load. Applied changes include inserts, updates, and removal of items.
	store_changes_enabled [bool]	Stores changes in Change tables. This value and the audit_changes_enabled value are mutually exclusive.
	audit_changes_enabled [bool]	Stores changes in a single audit

Parameter Name	Value	Description
		table. This value and the store_changes_enabled_value are mutually exclusive.
Task Stop reason	NONE	Indicates that a task is running and no Stop reason is prevalent.
	NORMAL	Indicates that the task was stopped by the user.
	RECOVERABLE_ERROR	Indicates that the task is still active, but that there is a temporary problem, such as a missing connection. As soon as the error state is resolved, Replicate restarts the task.
	FATAL ERROR	Indicates that the task stopped and the error must be resolved manually. The task cannot be started again until the error has been resolved.
	FULL_LOAD_ONLY_FINISHED	Indicates that the task only finished full load.
	STOPPED_AFTER_FULL_LOAD	Indicates that the task stopped after full load. Cached changes may or may not have been applied.
	STOPPED_AFTER_CACHED_EVENTS	Indicates that the task stopped after cached changes were applied.
	EXPRESS_LICENSE_LIMITS_REACHED	The task definition includes actions that are not included with Express license privileges.
	STOPPED_AFTER_DDL_APPLY	Indicates that the task stopped after DDL statements were applied.
	STOPPED_LOW_MEMORY	Indicates that the task stopped due to low memory.
	STOPPED_LOW_DISK	Indicates that the task stopped due to low disk space.
Replication profile	UNIDIRECTIONAL	Data is replicated from a source to a target.

Parameter Name	Value	Description
	BIDIRECTIONAL	Changes to the source are replicated to the target, and vice versa.
	LOG_STREAM_STAGING	Changes are captured from a single source and stored on Replicate Server for replication to one or more targets.
Source type	Source and target endpoint types should be specified in the same format that they appear in the Type drop-down list (when adding a new endpoint in AEM). For information on how to add an endpoint in AEM, refer to the <i>AEM Setup and User Guide</i> .	
Target type		
Run options	RESUME_PROCESSING	Resumes task execution from the point that it was stopped.
	RELOAD_TARGET	Re-starts the full-load replication process if the task was previously run.
	RESUME_PROCESSING_FROM_TIMESTAMP	Starts the CDC replication task from a specific point.
	RECOVER_USING_LOCALLY_STORED_CHECKPOINT	Recover a task using the recovery state stored locally in the task folder (located under the Data folder).
	•RECOVER_USING_CHECKPOINT_STORED_ON_TARGET	Recover a task using the CHECKPOINT value from the attrep_txn_state table (created in the target database).
	METADATA_ONLY_RECREATE_ALL_TABLES	Recreates the target tables defined for full load.
	METADATA_ONLY_CREATE_MISSING_TABLES	Creates missing target tables, including Change Tables.

Parameter Name	Value	Description
Request state	SUCCESS	Connection to endpoint is valid
	FAILURE	Connection to endpoint is not valid

3 | AEM .NET SDK

This chapter explains how to use the AEM .NET SDK and the lists the available methods.

In this chapter:

[Prerequisites](#)

[How To](#)

[Authentication and Authorization](#)

[Error Handling](#)

[PutServerLicense](#)

[GetServerDetails](#)

[PutServer](#)

[PutServerAcl](#)

[GetServer](#)

[GetServerAcl](#)

[GetServerList](#)

[DeleteServer](#)

[Syntax](#)

[DeleteServerAcl](#)

[GetTaskList](#)

[GetTaskDetails](#)

[DeleteTask](#)

[ExportTask](#)

[ImportTask](#)

[StopTask](#)

[RunTask](#)

[GetEndpointList](#)

[DeleteEndpoint](#)

[ExportAll](#)

[ImportAll](#)

[ReloadTable](#)

[TestEndpoint](#)

[Parameters](#)

Prerequisites

General Prerequisites

Before using the AEM .NET SDK, make sure that:

- » Attunity Enterprise Manager has been installed.
- » The AEM service is active.
- » The relevant permissions have been granted.

.NET SDK Prerequisites

The `<AEM_Installation_Folder>/clients/dotnet/` folder contains the following required files:

- » **AemRestClient.dll**
- » **Newtonsoft.Json.dll**

How To

This section describes how to use the AEM .NET SDK. To help you better understand how to implement the available methods, a code sample and a readme file that describes the code are located in the `<AEM_Installation_Folder>/clients/dotnet` folder.

To be able to use the AEM .NET SDK:

1. Create a project which references the **AemRestClient.dll** and **Newtonsoft.Json.dll** files
2. Create the `AemRestClient` object using one of the following constructors:
 - » `public AemRestClient(ICredentials credentials, string url = "https://localhost/attunityenterprisemanager", bool verifyCertificate = true);`
 - » `credentials` – See below.
 - » `url` – The URL to the AEM server. The URL must begin with "https".
 - » `verifyCertificate` – See below.
 - » `public AemRestClient(ICredentials credentials, string host, int port, string urlSuffix = "attunityenterprisemanager", bool verifyCertificate = true);`
 - » `credentials` – See below.
 - » `host` – The machine on which AEM is installed.
 - » `port` – The AEM server port (usually 443).
 - » `urlSuffix` – The part of the AEM URL that follows the host and port (usually `attunityenterprisemanager`).
 - » `verifyCertificate` – See below.

Note When `verifyCertificate` is set to **true** there must be valid certificate on the AEM machine. When set to **false**, AEM client will not validate the server certificate.

Creating Credentials

```
var credentials = new NetworkCredential
    {
        UserName = "USERNAME",
        Password = "PASSWORD",
        Domain = "DOMAIN"
    };
```

Creating a Client Object

```
_client = new AemRestClient(credentials, "localhost", 443, false);
```

Using Client Methods to Get/Set Data on AEM

After creating credentials and a client object, you can call the client methods to get/set data from AEM using the public APIs.

For example:

```
_client.GetServerList()
_client.GetServerDetails(serverName)
_client.ExportTask(serverName, taskName);
```

Authentication and Authorization

The `AemRestClient` user and password need to be the user and password that are defined in users or groups in AEM ACLs in at least one level (e.g AEM level, All Servers level, etc,) with at least Viewer role.

Error Handling

When a REST request fails, the HTTP response code is set to an error code. Information about the error is returned in the payload as an error response.

An error response has the following structure:

Class: `AemClientException` that inherits from `Exception` class and has the following fields:

`ErrorCode`

`Message`

This section lists the generic messages that apply to most of the API functions. Errors that are specific to a particular API function appear in the section for that API function.

Error	Message	Description
UNAUTHORIZED_REQUEST	Unauthorized Request.	The user is not authorized to perform the requested action (e.g. deleting a task).
INVALID_SESSION_ID	The session has expired or the session ID is not valid.	Session expired or invalid.
DESERIALIZE_TO_TYPE	Failed to deserialize json to type {type}: {message}	Returned when the JSON format is invalid.
AEM_SERVER_NOT_FOUND	The requested server {server} could not be found.	The requested server cannot be found.
AEM_SERVER_NOT_MONITORED	The requested server {server} is not monitored.	The requested server is not being monitored and thus the information is not accessible.
AEM_SERVER_NOT_CONNECTED	The requested server "{server}" cannot be reached at this time. Message: {message}	The desired information cannot be retrieved as the requested server is not connected.
AEM_SERVER_LICENSE_EXPIRED	The license for requested server {server} has expired.	The requested server license has expired.
AEM_SERVER_INVALID_LICENSE	The license for requested server {server} is not valid.	The requested server license is not valid.
LICENSE_NOT_FOUND	You need to register a Replication Management license in order to use Attunity Enterprise Manager. To register or obtain a license, open the Attunity Enterprise Manager console and follow the instructions.	Replication Management license was not found. For a user who is permitted to Register AEM license.
LICENSE_NOT_FOUND_CONTACT_ADMIN	An Enterprise Manager Admin needs to register a Replication Management license before you can use the product. To obtain a license, contact your Attunity Sales Representative with the Enterprise Manager machine name (which is displayed when you open the Enterprise Manager console).	Replication Management license was not found. For a user who is NOT permitted to Register AEM license.
LICENSE_	{Module} evaluation license has	{Module} is one of the following:

Error	Message	Description
EVALUATION_EXPIRED	expired.	<ul style="list-style-type: none"> » Replication Management » Replication Analytics
LICENSE_TERM_EXPIRED	{Module} license has expired.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
LICENSE_INVALID_SIGNATURE	The {Module} license signature is invalid.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
LICENSE_HOST_MISMATCH	The host name in the {Module} license does not match the Enterprise Manager machine name.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
AEM_MISSING_FIELD	The "{fieldName}" field is missing from the request.	When a mandatory field is missing from the request or appears empty

PutServerLicense

Registers a license on a specific server via AEM.

Required User Role: Admin on the specified server.

Syntax

```
public void PutServerLicense(
    string payload,
    string server
);
```

Parameters

Parameter	Type	Description
payload	string	The license to register on the server

Parameter	Type	Description
		[stream]. This is the license that was provided by your Attunity Sales Representative. Expected format: Text or JSON. Currently refers to the Replicate license only.
server	string	The name of the server.

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_PUT_SRV_LIC_INNER_ERR	Failed to put license for server "{server}". Error: "{message}"	Returned if AEM encounters an error/exception when trying to register the license on the specified server.
AEM_SRV_LIC_INVALID_FORMAT	The license file format is corrupt.	Returned when the contents of the license file are invalid.

GetServerDetails

Retrieves details about the specified server.

Required User Role: Viewer

Syntax

```
public AemGetServerDetailsResp GetServerDetails(
    string server
);
```


Parameters

Parameter	Type	Description
server	string	The specified server name in AEM.

Return Values

AemGetServerDetailsResp

Parameter	Type	Description
ServerDetails	AemServerDetails	ReplicateServerDetails or ComposeServerDetails that are inherited from AemServerDetails
Configuration		
Host	string	The host name or IP address of the Replicate/Compose Server machine.
Platform	AemPlatform { UNKNOWN = 0, WINDOWS = 1, LINUX = 2 }	The platform on which the Replicate/Compose Server machine is installed.
Port	string	The port through which the Replicate/Compose Server machine is accessed.
UserName	string	The user name for connecting to the Replicate/Compose Server machine.
Description	string	The server description.

Parameter	Type	Description
LastConnection	string	The date and time of the last successful sync/retrieval of tasks and messages.
License	ApiLicense	
DaysToExpiration	int	The number of days left before the license expires.
Expiration	string	The expiration date of the server license.
IssueDate	string	When the license was issued.
State	<pre>AemLicenseState { VALID_LICENSE = 0, INVALID_LICENSE_ CHECKSUM = 1, EXPIRED_LICENSE = 2, NO_LICENSE = 3, MACHINE_NOT_LICENSED = 4, INVALID_LICENSE = 5 }</pre>	The current license state (e.g. valid, expired, etc.).
Message	string	The error message if AEM fails to connect to the Replicate/Compose Server machine.
Name	string	The name of the

Parameter	Type	Description
		server in AEM.
ResourceUtilization	AemServerUtilization	
	int	The sum of CPU percentage of Replicate server and all running tasks processes.
AttunityCpuPercentage		
	long	The amount of disk space that the server is currently consuming, in MB. This is the sum of disk usage for all tasks on this server.
DiskUsageMb		
	int	The CPU percentage of the machine where Replicate is installed.
MachineCpuPercentage		
	long	The amount of memory that the server is currently consuming, in MB. This is the sum of memory usage for all active tasks on this server, excluding stopped tasks.
MemoryMb		
State	AemServerState { NOT_MONITORED = 0, MONITORED = 1, ERROR = 2 }	The state of the server.

Parameter	Type	Description
AemTasksSummary	TaskSummary	
Error	int	The number of tasks that encountered a fatal error.
Recovering	int	The number of recovering tasks
Running	int	The number of running tasks.
Stopped	int	The number of stopped tasks.
Total	int	The total number of tasks, regardless of state.
Version	string	The Replicate/Compose Server version.

Notes

- » The return value -1 means N/A.
- » Parameters related to Disk, Memory, Attunity CPU, and Machine CPU usage are not available for Compose servers. For Compose servers, these parameters will be returned as -1.
- » Parameters related to Attunity CPU and Machine CPU usage are only available for Replicate 6.2 and above. For earlier Replicate versions, these parameters will be returned as -1.
- » For servers that are in an error state or not monitored, parameters related to Disk and Memory usage will be returned as -1.

Errors

Error	Message	Description
AEM_SERVER_NOT_FOUND	Replicate server {server} could not be found.	Server name unknown to AEM.

See [Error Handling](#).

PutServer

Adds a new Replicate/Compose Server or updates the server definition (Connection Properties) if the specified server already exists. This method can be used together with AemGetServer in order to update the connection properties of an existing server.

First call AemGetServer, then edit the returned properties as required, and finally, call AemPutServer.

Required User Role

- » For adding a new server - Admin on all servers.
- » For updating an existing server - Admin on the specified server.

Syntax

```
public void PutServer(
    AemServer payload,
    string server
);
```

Parameters

Parameter	Type	Description
payload	AemServer	AemReplicateServer or AemComposeServer that is inherited from AemServer.
Description	string	The server description.
Host	string	The host name or IP address of the server.
Monitored	bool	Whether to retrieve tasks and messages from this server or not.
Name	string	The name of the server.
Password	string	The password to connect to the Replicate/Compose Server. Note The password identifier (GUID) that is returned by GetServer is valid only for the session in which it was generated. Using it in another session (for example as input for PutServer) will result in exception.
Port	string	The port through which the server is accessed.
Username	string	The user name to connect to the Replicate/Compose Server.
server	string	The name of the server.

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
DESERIALIZE_TO_TYPE	"Failed to deserialize json to type AemServer: {message}"	Returned when the JSON format is invalid format. For example, such an error will be returned if the JSON contains an unknown role.
AEM_PUT_SERVER_INNER_ERR	Failed to put server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to PUT the server.
AEM_INVALID_SERVER_TYPE	Server type {ServerType} for server "{ServerName}" is not valid.	Returned when the an invalid server type is specified.
AEM_NAME_URL_MISMATCH	The name of the server in the request does not match the one that is specified in the URL.	Returned when the name of the server in the request does not match the one that is specified in the URL.
AEM_EMPTY_HOST	The host is missing from the request.	Returned when the host is missing from the request.
AEM_EMPTY_PORT	The port is missing from the request.	Returned when the port is missing from the request.
AEM_EMPTY_USERNAME	The username is missing from the request.	Returned when the user name is missing from the request.
AEM_EMPTY_PASSWORD	The password is missing from the request.	Returned when the password is missing from the request.
AEM_INVALID_PORT	The port is invalid.	Returned when the specified port is not valid.
AEM_INVALID_	The user name is invalid.	Returned when the

Error	Message	Description
USERNAME	User names cannot exceed 104 characters and can contain all Unicode characters except for the following characters: Forward slash (/), Left square bracket ([), Right square bracket (]), Colon (:), Semicolon (;), Vertical bar (), Equal sign (=), Plus sign (+), Asterisk (*), Question mark (?), Left angle bracket (<), Right angle bracket (>), Double quote (\").	specified user name is not valid.
AEM_INVALID_DESC	The description is invalid. Descriptions cannot exceed 250 characters.	Returned when the description exceeds 250 characters.
AEM_INVALID_HOST	The host is invalid. Hosts cannot exceed 64 characters and can only contain letters (a-z or A-Z), digits, spaces, dots (.), dashes (-), and underscores (_).	Returned when the server host name exceeds 64 characters or contains invalid characters.
AEM_INVALID_NAME	The name of the server is invalid. Server names cannot exceed 64 characters and can only contain letters (a-z or A-Z), digits, spaces, dots (.), dashes (-), and underscores (_).	Returned when the server name exceeds 64 characters or contains invalid characters.
AEM_HOST_PORT_ALREADY_EXIST	Host {name/IP} and port {number} are already in use by another server.	Returned when both the server host name/IP address and the server port are already in use by another server.

PutServerAcl

Puts an explicit ACL for a specific server in AEM. The method will replace any existing explicit ACL with the ACL in the request. The request also includes a Boolean flag for specifying whether or not the server should inherit ACLs from its ancestors (in addition to its explicitly defined ACLs).

The inherited ACLs (i.e., the ACLs of the server's ancestors) are not affected by this method.

The `AemPutServerAcl` can be used together with the `AemGetServerAcl` method in order to update an existing server's ACL. First call `AemGetServerAcl`, then edit the returned roles as required, and finally, call `AemPutServerAcl`.

Behavior when putting a partial request:

When the request body includes only some of the roles (as opposed to all four of them), only the roles specifically defined in the request body will be set on the server; roles that are missing or empty will be inherited, but only if the following are true:

- » The `disable_inheritance` flag is set to "True".
- » The roles that are missing/empty in the request are defined for the ancestors.

Behavior on conflicts:

If the `disable_inheritance` flag is set to "False" and the explicit roles in the request conflict with existing inherited roles, then the explicit roles will take precedence. For example, if the request defines user A as a Viewer on **MyServer** and user A is also defined as an Admin on All Servers, then user A will be defined as an Admin on All Servers but as a Viewer on **MyServer**.

Note The user permissions in AEM are completely independent of the user permissions in Replicate. Consequently, `AemPutServerAcl` will affect the server's AEM user permissions, but will *not* affect Replicate's user permissions.

Moreover, when performing an operation via AEM, the user permissions defined for the server entity in AEM apply, whereas when performing an operation directly via the Replicate Console, the user permissions defined in Replicate apply.

Note Defining the same user/group in different roles is not allowed. However, if the same user or group is defined in different roles but with a different case (e.g. Mike vs. mike or Analysts vs. ANALYSTS), no error will be returned and the strongest role will take precedence.

Required User Role: Admin on the specified server.

Syntax

```
public void PutServerAcl(  
    AemAuthorizationAcl payload,  
    string server  
);
```


Parameters

Parameter	Type	Description
payload	AemAuthorizationAcl	
DisableInheritance	bool	If set to "true", the server does not inherit ACLs from its ancestors (in addition to its explicit ACLs). If set to "false", the server inherits ACLs from its ancestors, in addition to any explicit ACLs
AdminRole	AemRoleDef	Users and/or groups assigned as Admin role
DesignerRole	AemRoleDef	Users and/or groups assigned as Designer role
OperatorRole	AemRoleDef	Users and/or groups assigned as Operator role
ViewerRole	AemRoleDef	Users and/or groups assigned as Viewer role
Groups	List<AemGroupRef>	Groups assigned as the role
Name	string	The group name
Users	List<AemUserRef>	Users assigned as the role
Name	string	The user name
server	string	The name of the server

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
DESERIALIZE_TO_TYPE	"Failed to deserialize json to type AemAuthorizationAcl: {message}"	Returned when the JSON format is invalid format. For example,

Error	Message	Description
		such an error will be returned if the JSON contains an unknown role.
AEM_PUT_SERVER_ACL_INNER_ERR	Failed to put ACL of server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to put the server's ACL.
AEM_NO_DOMAIN_IN_USER	User "{userName}" must be preceded by a domain name, separated by a backslash. Example: domain_name\user_name.	Returned when the domain is missing from the user name.
AEM_NO_DOMAIN_IN_GROUP	Group "{groupName}" must be preceded by a domain name, separated by a backslash. Example: domain_name\group_name.	Returned when the domain is missing from the group name.
AEM_NO_ADMIN_ON_SERVER	Requested server "{serverName}" has no admin user. At least one user or group must be assigned to the "admin" role.	Returned when there is no admin on the server. Possible reasons: <ul style="list-style-type: none"> » The request JSON is set to <code>disable_inheritance=true</code> and the explicit admin role in the JSON is empty. » The JSON is set to <code>disable_inheritance=true</code>, the explicit admin role in the JSON is empty, and the parent levels do not have an admin user to inherit.
AEM_USER_ASSIGNED_TO_MULTIPLE_ROLES	User "{userName}" is assigned to multiple roles. Users can only be assigned to a single role.	Returned when a user is assigned to multiple roles.
AEM_GROUP_ASSIGNED_TO_MULTIPLE_ROLES	Group "{groupName}" is assigned to multiple roles. Groups can only be assigned to a single role.	Returned when a group is assigned to multiple roles.
AEM_USER	"{userName/groupName}" is	Returned either when the

Error	Message	Description
GROUP_MULTIPLE_ASSIGNED	assigned to multiple roles or to the same role twice. Users/groups can only be assigned once, and to a single role.	specified user already exists as a group in the same/another role, or the specified group already exists as a user in the same/another role.

GetServer

Retrieves the definition (Connection Properties) of the specified server. This method can be used together with PutServer in order to update the connection properties of an existing server. First call GetServer, then edit the returned properties as required, and finally, call PutServer.

Required User Role: Operator on server.

Syntax

```
public AemServer GetServer(
    string server
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server to retrieve.

Return Values

AemServer (AemReplicateServer or AemComposeServer that inherited from AemServer)

Parameter	Type	Description
Description	string	The server description.
Host	string	The host name or IP address of the server.
Monitored	bool	Whether to retrieve tasks and messages from this server or not.
Name	string	The name of the server.
Password	string	The password to connect to the

Parameter	Type	Description
		Replicate/Compose Server. Note The password identifier (GUID) that is returned by GetServer is valid only for the session in which it was generated. Using it in another session (for example as input for PutServer) will result in exception.
Port	string	The port through which the server is accessed.
Username	string	The user name to connect to the Replicate/Compose Server.

Errors

See [general errors](#).

GetServerAcl

Retrieves the explicit ACL defined in AEM for the specified server, including a Boolean indication if ACL inheritance is disabled or enabled for the server.

The method returns the explicit ACL only. In other words, it does not return inherited ACLs.

If all of the servers ACLs are inherited (i.e. no ACL was explicitly defined for the server), an error will be returned indicating that no ACL was found.

This method can be used together with `AemPutServerAcl` in order to update an existing server's ACL. First call `AemGetServerAcl`, then edit the returned roles as required, and finally, call `AemPutServerAcl`.

Required User Role: Operator on the specified server.

Syntax

```
public AemAuthorizationAcl GetServerAcl(
    string server
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server where the ACL is located.

Return Values

AemAuthorizationAcl

Parameter	Type	Description
DisableInheritance	bool	If set to "true", the server does not inherit ACLs from its ancestors (in addition to its explicit ACLs). If set to "false", the server inherits ACLs from its ancestors, in addition to any explicit ACLs
AdminRole	AemRoleDef	Users and/or groups assigned as Admin role
DesignerRole	AemRoleDef	Users and/or groups assigned as Designer role
OperatorRole	AemRoleDef	Users and/or groups assigned as Operator role
ViewerRole	AemRoleDef	Users and/or groups assigned as Viewer role
Groups	List<AemGroupRef>	Groups assigned as the role
Name	string	The group name
Users	List<AemUserRef>	Users assigned as the role
Name	string	The user name

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_GET_SERVER_ACL_INNER_ERR	Failed to get ACL of server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to get the server ACL.
AEM_SERVER_HAS_NO_ACL	ACL for server "{server}" could not be found.	Returned if no explicit ACL is defined for the server.

Error	Message	Description
		<p>Note A server that does not have its own explicit ACL inherits the ACL from its ancestors. Inherited ACLs are <i>not</i> returned by this method.</p>

GetServerList

Retrieves a list of servers under AEM management as well as each server's properties.

Required User Role: Viewer.

Syntax

```
public AemGetServerListResp GetServerList(
);
```

Parameters

N/A

Return Values

AemGetServerListResp

Value	Type	Description
ServerList	List<AemServerInfo>	ReplicateServerInfo or ComposeServerInfo that inherit from AemServerInfo.
Description	string	The description of the server
Host	string	The host name or IP address of the server.
LastConnection	string	The date and time of the last successful

Value	Type	Description
		sync/retrieval of tasks and messages.
Message	string	The error message if AEM fails to connect to the server.
Name	string	The name of the server.
Platform	AemPlatform { UNKNOWN = 0, WINDOWS = 1, LINUX = 2 }	AemPlatform
Port	string	The port through which the server is accessed.
State	AemServerState { NOT_MONITORED = 0, MONITORED = 1, ERROR = 2 }	AemServerState
Version	string	The Replicate/Compose Server version

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_SERVER_NOT_FOUND	Replicate server {server} could not be found.	Server name unknown to AEM.

DeleteServer

Description

When this method is called, AEM will:

- » Delete the specified server from AEM
- » Stop monitoring any tasks that were defined on the server
- » Delete all messages related to the server from the Message Center
- » Delete all user roles defined for the server, the server tasks, and the server endpoints

Note The above operations will be performed, regardless of whether the server is currently being monitored or in an error state.

Required User Role: Admin on server.

Syntax

```
public void DeleteServer(
    string server
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server to be deleted.

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Text	Description
AEM_SERVER_NOT_FOUND	Requested server "{server}" could not be found.	The server name is unknown to AEM.

Error	Text	Description
AEM_DELETE_SERVER_INNER_ERR	Failed to delete requested server "{server}".	AEM encountered an error/exception when trying to delete the server.

DeleteServerAcl

Deletes the explicit ACL defined in AEM for the specified server. Inherited ACLs are not affected by this method. Once the explicit ACL is deleted from the server, all ACLs will be automatically inherited from the server's ancestors.

Required User Role: Admin on the specified server.

Syntax

```
public void DeleteServerAcl(
    string server
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server whose ACL needs to be deleted.

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_DELETE_SERVER_ACL_INNER_ERR	Failed to delete ACL of server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to delete the server's ACL.
AEM_SERVER_HAS_NO_ACL	ACL for server "{server}" could not be found.	Returned when the specified server has no explicit ACL defined.

GetTaskList

Receive a list of tasks per selected and authorized server. For each task, the API returns a few values.

Required User Role: Viewer

Syntax

```
public AemGetTaskListResp GetTaskList(
    string server
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server on which the tasks reside.

Return Values

AemGetTaskListResp

Value	Type	Description
TaskList	List<AemTaskInfo>	An array of Endpoint objects.
Name	string	The name of the task
State	AemTaskState	<pre>{ STOPPED = 0, RUNNING = 1, ERROR = 2, RECOVERY = 3 }</pre>
StopReason	AemTaskStopReason	The reason the task stopped
		<pre>{ NONE = 0, NORMAL = 1, RECOVERABLE_ ERROR = 2,</pre>

Value	Type	Description
	FATAL_ERROR = 3, FULL_LOAD_ ONLY_FINISHED = 4, STOPPED_ AFTER_FULL_ LOAD = 5, STOPPED_ AFTER_CACHED_ EVENTS = 6, EXPRESS_ LICENSE_ LIMITS_ REACHED = 7, STOPPED_ AFTER_DDL_ APPLY = 8, STOPPED_LOW_ MEMORY = 9, STOPPED_LOW_ DISK_SPACE = 10 }	
Message	string	The message if the task stopped due to an error.
AssignedTags	array	Returns the custom tags assigned to the task. If no tags are assigned to the task, an empty array will be returned.

Errors

See [general errors](#).

GetTaskDetails

Retrieves details about a selected and authorized task. The API returns full monitoring information related to the selected task.

Required User Role: Viewer.

Syntax

```
public AemGetTaskDetailsResp GetTaskDetails(
    string server,
    string task
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server.
task	string	The name of the task.

Return Values

AemGetTaskDetailsResp

Value	Type	Description
Task	AemTaskInfoDetailed	
Name	string	The name of the task.
CdcEventCounters	AemTaskCdcEventCounters	All numeric data concerning CDC events
AppliedDdlCount	long	The total number of metadata changes, such as add column
AppliedDeleteCount	long	The number of records deleted in total for all tables
AppliedInsertCount	long	The number of records added in total for all tables
AppliedUpdateCount	long	The number of records updated in

Value	Type	Description
		total for all tables
CdcLatency	AemCdcLatency	CDC latency information
SourceLatency	string	The time gap between the original change in the source endpoint and capturing it, in hh:mm:ss
TotalLatency	string	The overall latency (source latency + target latency + apply latency), in hh:mm:ss
CdcThroughput	AemCdcThroughput	Indicates how fast the table records are being replicated to the target endpoint (by number or volume of records). Refers only to the current/last CDC.
SourceThroughputRecordsCount	AemCdcThroughputItem	The current source throughput, in rec/sec
SourceThroughputVolume	AemCdcThroughputItem	The current source throughput, in kbyte/sec
TargetThroughputRecordsCount	AemCdcThroughputItem	The current target throughput, in rec/sec
TargetThroughputVolume	AemCdcThroughputItem	The current target throughput, in kbyte/sec
Current	long	

Value	Type	Description
CdcTransactionsCounters	AemCdcTransactionsCounters	All numeric data concerning CDC transactions
AppliedCommittedTransactionCount	long	The number of transactions committed.
AppliedRecordsCommittedCount	long	The sum of all records/events in all Completed transactions
AppliedRecordsInProgressCount	long	The sum of all records/events in all In-Progress transactions
AppliedTransactionsInProgressCount	long	The number of transactions in progress.
AppliedVolumeCommittedMb	long	The sum of all volume/events in all Completed transactions, in MB.
CommitChangeRecordsCount	long	The number of COMMIT change records.
IncomingAccumulatedChangesOnDiskCount	long	The number of changes accumulated on disk until source commit
IncomingAccumulatedChangesInMemoryCount	long	The number of changes accumulated in memory until source commit.
IncomingApplyingChangesInMemoryCount	long	The number of changes in memory during

Value	Type	Description
		apply and until target commit.
IncomingApplyingChangesOnDiskCount	long	The number of changes on disk during apply and until target commit.
RollbackChangeRecordsCount	long	The number of ROLLBACK change records.
RollbackChangeVolumeMb	long	The volume of ROLLBACK changes, in MB.
RollbackTransactionCount	long	The number of changes in memory during apply and until target commit.
FullLoadCompleted	bool	
FullLoadCounters	AemTaskFullLoadCounters	All numeric data concerning Full Load events.
EstimatedRecordsForAllTablesCount	long	The estimated number of records remaining to be loaded into the target endpoint.
RecordsCompletedCount	long	The total number of records that have completed loading into the target endpoint.
TablesCompletedCount	int	The number of tables that have been loaded into the target endpoint.

Value	Type	Description
TablesLoadingCount	int	The number of tables that are currently being loaded into the target endpoint.
TablesQueuedCount	int	The number of tables that are waiting to be loaded due to an error.
TablesWithErrorCount	int	The number of tables that could not be loaded due to an error.
FullLoadEnd	string	Indicates whether the full load process has ended.
FullLoadStart	string	The start time of the full load process. Format: YYYY MM DD Timezone: UTC
FullLoadThroughput	AemFullLoadThroughput	
SourceThroughputRecordsCount	int	The current source throughput, in rec/sec.
SourceThroughputVolume	int	The current source throughput, in kbyte/sec.
TargetThroughputRecordsCount	int	The current target throughput, in rec/sec.
TargetThroughputVolume	int	The current target throughput, in kbyte/sec.

Value	Type	Description
MemoryMb	long	The current utilization of memory, in MB. A task's memory utilization is sampled every 10 seconds. When the task is not running, the value is set to zero (0).
CpuPercentage		The current CPU usage of the Replicate task process.
		<p>Notes</p> <p>Only available for Replicate tasks running on Replicate 6.2 and above. When not available, this parameter will be returned as -1.</p>
DiskUsageMb	long	The current utilization of disk space, in MB. A task's disk utilization is sampled every minute.
DataErrorCount	long	The total number of data errors in all tables involved in the task. The count is affected by data errors and the

Value	Type	Description
		Reset Data Errors option available when you drill down to a task.
Options	AemCommonSettings	
ApplyChangesEnabled	bool	See Task Options .
AuditChangesEnabled	bool	See Task Options .
FullLoadEnabled	bool	See Task Options .
StoreChangesEnabled	bool	See Task Options .
ReplicateProfile	AemReplicateTaskProfile <pre>{ UNIDIRECTIONAL = 1, BIDIRECTIONAL = 2, LOG_STREAM_STAGING = 3 }</pre>	AemReplicateTaskProfile
SourceEndpoint	TaskEndpoint	
Name	string	The name of the source endpoint.
Type	string	The source endpoint type.
TargetEndpoint	TaskEndpoint	
Name	string	The name of the target endpoint.
Type	string	The target endpoint type.
State	AemTaskState <pre>{ STOPPED = 0, RUNNING = 1, ERROR = 2, }</pre>	The current state of the task.

Value	Type	Description
	<pre> RECOVERY = 3 } </pre>	
TaskStopReason	<pre> AemTaskStopReason { NONE = 0, NORMAL = 1, RECOVERABLE_ ERROR = 2, FATAL_ERROR = 3, FULL_LOAD_ ONLY_FINISHED = 4, STOPPED_ AFTER_FULL_ LOAD = 5, STOPPED_ AFTER_CACHED_ EVENTS = 6, EXPRESS_ LICENSE_ LIMITS_ REACHED = 7, STOPPED_ AFTER_DDL_ APPLY = 8, STOPPED_LOW_ MEMORY = 9, STOPPED_LOW_ DISK_SPACE = 10 } </pre>	The reason the task stopped.
LogStreamStaging	string	If the task is writing to/reading from the Log Stream staging folder, the name of the associated Log Stream Staging task will be

Value	Type	Description
		returned. Otherwise, an empty string will be returned.
Message	string	The message if the task stopped due to an error.
AssignedTags	array	Returns the custom tags assigned to the task. If no tags are assigned to the task, an empty array will be returned.

Errors

Error	Message	Description
AEM_TASK_NOT_FOUND	Replicate task{task} on server {server} could not be found.	The task name is unknown to AEM.

DeleteTask

Deletes the specified task. The task's logs will be deleted only if `deletetasklogs=true` is set.

Required User Role: Designer.

Syntax

```
public void DeleteTask(
    string server,
    string task,
    bool deletetasklogs = false
);
```

Parameters

Parameter	Type	Description
server	string	The server where the task is defined.
task	string	The task to be deleted.
deletetasklogs	bool	Whether to delete the task logs or not.

Errors

Error	Message	Description
AEM_TASK_NOT_FOUND	Replication task {task} on server {server} could not be found.	Returned if the task name is unknown to AEM.
AEM_DELETE_TASK_INNER_ERR	Replication task {task} on server {server} could not be deleted due to an error.	Returned if AEM encounters an error/exception when trying to delete the task.
AEM_DELETE_TASK_ERR	Replication task {task} on server {server} could not be deleted due to an error. {2}	Returned if AEM encounters an error when trying to delete the task.
AEM_TASK_NOT_STOPPED	Replication task {task} on server {server} must be stopped before it can be deleted.	Returned if the replication task was running when <code>AemDeleteTask</code> attempted to delete it.

ExportTask

Export definitions from the selected task on the selected server. The definitions always include task settings, tables/table patterns (include/exclude), table settings and global transformations. The endpoint definition is only exported along with the task definition if with `endpoints=true` is set.

Required User Role: Operator.

Syntax

```
public string ExportTask(
    string server,
    string task,
    bool withendpoints = false
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server on which the task is defined.
task	string	The task to be exported.
withendpoints	bool	Whether or not to export the endpoint definitions as well.

Return Values

Exported task JSON file as a string

Errors

Error	Message	Description
AEM_METHOD_NOT_SUPPORTED_VERSION	AemExportTask is only supported on Replicate 5.5 or above.	AemExportTask is only supported on Replicate 5.5 or above.
AEM_EXPORT_TASK_NO_PERMISSION_ON_ENDPOINT	Failed to export task {task} from Replicate server {server} as the logged in user does not have permission to access one or both of the task's endpoints.	Export all cannot be carried out because the user does not have permissions on one or more endpoints.

ImportTask

Import a single task's JSON definitions provided in the request body into the requested server repository on the selected server.

The ImportTask method enables importing all valid JSON definitions provided in the request body.

This includes task settings, tables/table patterns (include/exclude), table settings and global transformations.

Information about endpoints is included if it was included in the JSON file.

When you import a task, Items that existed in the target server before the import and have no new JSON definition in the request body are not modified and not removed. This means that ImportTask provides no way of removing old definitions that are no longer needed.

Required User Role: Designer on relevant task.

If endpoint definitions are included in the JSON definition, a user must also be Designer on the relevant endpoints.

Syntax

```
public void ImportTask(  
    string payload,  
    string server,  
    string task  
);
```

Parameters

Parameter	Type	Description
payload	string	A JSON document to import
server	string	The name of the server to import to.
task	string	Name of the task to import

Return Values

N/A

Errors

Error	Message	Description
AEM_IMPORT_TASK_NO_PERMISSION_ON_ENDPOINT	Failed to import task {task} to replication server {server} as the logged in user does not have permission to add or modify endpoints.	The task cannot be imported because it includes endpoint definitions, and the user does not have permissions to insert endpoints.

Error	Message	Description
AEM_IMPORT_TASK_CONTAIN_ALIEN_ITEMS	Failed to import task {task} to replication server {server} as the JSON file contains unsupported objects.	The task cannot be imported because the stream contains items that cannot be imported (such as remote machines).
AEM_IMPORT_TASK_NAME_DIFFER	Failed to import task {task} to replication server {server} as the JSON file contains conflicting tasks.	The task cannot be imported because the stream contains conflicting tasks.
AEM_IMPORT_TASK_CONTAINS_MULTIPLE_TASKS	Failed to import task to replication server {server} as the JSON file contains multiple tasks. To import multiple tasks, use AemImportAll instead.	The task cannot be imported since the stream contains multiple tasks, and the method can only import a single task.
AEM_TASK_NOT_IMPORTABLE	Failed to import task {task} as the task is running on server {server}. Stop the task and then try again.	Occurs when trying to import a running task.
AEM_IMPORT_TASK_CONTENT_EMPTY	Failed to import task {task} to replication server {server} as the JSON file is empty.	The task cannot be imported as the specified JSON file is empty.
AEM_IMPORT_TASK_ENDPOINT_DIFFER	Failed to import task {task} to server {server} as the endpoint names in the JSON file's "task" and "databases" sections are not the same.	The task cannot be imported as the endpoint names in the specified JSON file's "task" and "databases" sections are different.
AEM_IMPORT_TASK_NO_ENDPOINT_IN_SERVER	Failed to import task {task} to replication server {server} as the {role} endpoint {endpoint} does not exist on the target server.	The task cannot be imported as one of the endpoints specified in the exported JSON file does not exist on the target server.

StopTask

Stop the selected task.

Required User Role: Operator.

Syntax

```
public AemStopTaskResp StopTask(
    string server,
    string task,
    int timeout = 30
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server.
task	string	The name of the task.
timeout	int	Time in seconds to wait until getting a response.

Return Values

AemStopTaskResp

Parameter	Type	Description
State	AemTaskState	The current state of the task. <pre>{ STOPPED = 0, RUNNING = 1, ERROR = 2, RECOVERY = 3 }</pre>
ErrorMessage	string	The description of the error

Errors

Error	Message	Description
AEM_TASK_	Replicate task {task} on server	Cannot stop a task that is

Error	Message	Description
ALREADY_STOPPED	{server} is already stopped.	in Stopped state.
AEM_STOP_TASK_INNER_ERR	Failed to stop Replicate task {0} on server {1}: <{2}>	An error occurred while trying to stop the task.
AEM_STOP_TASK_TIMEOUT	A timeout occurred when trying to stop Replicate task {0} on server {1}	A timeout occurred while trying to stop the task.

RunTask

Run the selected task according to the specified option.

Required User Role: Operator.

Syntax

```
public AemRunTaskResp RunTask(
    AemRunTaskReq payload,
    string server,
    string task,
    AemRunTaskOptions option = AemRunTaskOptions.RESUME_PROCESSING,
    int timeout = 30
);
```

Parameters

Parameter	Type	Description
payload	AemRunTaskReq	
Cdcposition	string	The <code>cdcposition</code> parameter can either be specified inline or in an external JSON file. The format for both is described in below. Required if the option (see below) = <code>RESUME_PROCESSING_FROM_TIMESTAMP</code> or <code>RECOVER_USING_CHECKPOINT_</code>

Parameter	Type	Description
		STORED_ON_TARGET
server	string	The name of the server on which to run the task.
task	string	The name of the task to run.
option	<pre>AemRunTaskOptions { RESUME_ PROCESSING = 1, RELOAD_ TARGET = 2, RESUME_ PROCESSING_ FROM_ TIMESTAMP = 3, METADATA_ ONLY_ RECREATE_ ALL_TABLES = 4, METADATA_ ONLY_ CREATE_ MISSING_ TABLES = 5, RECOVER_ USING_ LOCALLY_ STORED_ CHECKPOINT = 6, RECOVER_ USING_ CHECKPOINT_ STORED_ON_ TARGET = 7 }</pre>	
timeout	int	The time in seconds to wait for a response.

Return Value

AemRunTaskResp

Parameter	Type	Description
ErrorMessage	string	The description of the error.
State	AemTaskState	The current state of the task. <pre> { STOPPED = 0, RUNNING = 1, ERROR = 2, RECOVERY = 3 }</pre>

Errors

Error	Message	Description
AEM_TASK_ALREADY_RUNNING	Replicate task {task} on server {server} is already running.	The task cannot be run because it is already running.
AEM_TASK_IN_RECOVERY	Replicate task {task} on server {server} cannot be run as it is in a recovery state.	The task cannot be run because it is in Recovery state.
AEM_WRONG_OPTION_FOR_CDCPOSITION	Replicate task {task} on server {server} cannot be run with cdcposition {position} and option {option}. Change the option to RESUME_PROCESSING_FROM_TIMESTAMP or RECOVER_USING_CHECKPOINT_STORED_ON_TARGET.	When the option Tables are already loaded. Start processing changes from Timestamp is selected in the Advanced Run Options dialog box for a task, the option sent to the API must be RESUME_PROCESSING_FROM_TIMESTAMP.
AEM_CDC_POSITION_	The cdcposition parameter value	The cdcPosition parameter must follow this format: YYYY-MM-

Error	Message	Description
ERR_FORMAT	for Replicate task {task} on server {server} is not in the correct format ('YYYY-MM-DDThh:mm:ssZ').	DDThh:mm:ssZ Parameters: task name and server name
AEM_RUN_TASK_TIMEOUT	Replicate task {task} on server {server} timed out when requested to "Run".	The task does not assume a Running state or any other steady state (error o stopped).
AEM_RUN_TASK_INNER_ERR	Replicate task {task} on server {server} encountered an error when requested to run.	Replicate experienced an error/exception when trying to run the task.
AEM_RUN_TASK_NO_SRC_NO_TRG	Replicate task {task} on server {server} has no source or target endpoints.	Task validation revealed that the task is missing a source and a target.
AEM_RUN_TASK_NO_SRC	Replicate task {task} on server {server} has no source endpoint.	Task validation revealed that the task is missing a source.
AEM_RUN_TASK_TRG	Replicate task {task} on server {server} has no target endpoint.	Task validation revealed that the task is missing a target
AEM_RUN_TASK_NOT_FL_NOR_CDC	Replicate task {task} on server {server} cannot be run without at least one of the replication options enabled (Full Load, Apply Changes, or Store Changes).	Task validation of a unidirectional task revealed that the replication option definition for the task is missing (Full Load, Apply Changes, or Store Changes).
AEM_RUN_BIDI_TASK_NO_FL_NOR_CDC	Replicate task {task} on server {server} cannot be run without at least one of the replication options enabled (Full Load or Apply Changes).	Task validation of a unidirectional task revealed that the replication option definition for the task is missing (Full Load, Apply Changes, or Store Changes).

GetEndpointList

Retrieves a list of endpoints and their properties for the specified server.

Required User Role: Viewer.

Syntax

```
public AemGetEndpointListResp GetEndpointList(
    string server
```

);

Parameters

Parameter	Type	Description
server	string	The name of the server on which the endpoints are defined.

Return Values

AemGetEndpointListResp

Parameter	Type	Description
EndpointList	List<Endpoint>	An array of Endpoint objects.
Description	string	The endpoint description
IsLicensed	bool	Indicates whether the endpoint is licensed on this server.
Name	string	The endpoint name.
Role	EndpointRole	The endpoint role: SOURCE or TARGET. <pre> { ALL = 0, SOURCE = 1, TARGET = 2, BOTH = 3 } </pre>
Type	string	The endpoint type - for example, Oracle.

Errors

Error	Message	Description
AEM_ENDPOINT_LIST_INNER_ERR	Failed to retrieve endpoints list from Replicate server {name}.	Replicate experienced an error/exception when trying to retrieve the endpoint list.

DeleteEndpoint

Description

Deletes the specified endpoint. Note that an endpoint can only be deleted if it is not in use by any task.

Required User Role: Designer.

Syntax

```
public void DeleteEndpoint(  
    string server,  
    string endpoint  
);
```

Parameters

Parameter	Type	Description
server		The server where the endpoint is defined.
endpoint		The name of the endpoint to be deleted.

Return Values

N/A

Errors

Error	Message	Description
AEM_ENDPOINT_NOT_FOUND	Replicate endpoint {endpoint} on server {server} could not be found.	Endpoint name unknown to AEM.
AEM_DELETE_ENDPOINT_INNER_ERR	Failed to delete Replicate endpoint {endpoint} from server {server}.	Replicate encountered an error/exception when trying to delete the endpoint.
AEM_ENDPOINT_IS_IN_USE	Replicate endpoint {endpoint} on server {server} cannot be deleted as it is currently in use by one or more tasks.	The Replicate endpoint must be removed from its associated tasks before it can be deleted.

ExportAll

Export all definitions from the requested server repository on the selected server (server settings, tasks, endpoints, and so on). The definitions are exported to a JSON file.

Required User Role

- » AEM: Admin
- » Server: Admin
- » All Tasks: Designer
- » All Endpoints: Operator

Syntax

```
public string ExportAll(
    string server
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server containing the repository to be exported.

Return Values

Export JSON file as a string.

Errors

Error	Message	Description
AEM_METHOD_NOT_SUPPORTED_VERSION	AemExportAll is only supported on Replicate 5.5 or above.	The method requires Replicate 5.5 or above.
AEM_EXPORT_NO_PERMISSION_ON_TASK	Failed to export all tasks from Replicate server {server} as the logged in user does not have permission to export one or more of the defined tasks.	Export all cannot be carried out because the user does not have permissions on one or more tasks.
AEM_EXPORT_NO_PERMISSION_ON_ENDPOINT	Failed to export all tasks from server {server} as the logged in user does not have permission to export one or more of the defined endpoints.	Export all cannot be carried out because the user does not have permissions on one or more endpoints.

ImportAll

Import the JSON definitions provided in the request body into the requested server repository on the selected server. The ApiImportAll method uses "merge" semantics. In particular: All valid JSON definitions provided in the request body will be imported.

This includes server settings, task settings, endpoints, and other definitions.

Items that existed in the target server before the import and have no new JSON definition in the request body will not be modified and in particular will not be removed. This means that ApiImportAll provides no way of removing old definitions that are no longer needed.

Required User Role

- » AEM: Admin
- » Server: Admin
- » All Tasks: Designer
- » All Endpoints: Designer

Syntax

```
public void ImportAll(
    string payload,
```

```

        string server
    );

```

Parameters

Parameter	Type	Description
payload	string	A JSON document to import
server	string	The name of the server to import to.

Return Values

N/A

Errors

Error	Message	Description
AEM_METHOD_NOT_SUPPORTED_VERSION	AemImportAll is only supported on Replicate 5.2 or above.	The method requires Replicate 5.2 or above.
AEM_IMPORT_NO_PERMISSION_ON_TASK	Failed to import all tasks to replication server {server} as the logged in user does not have permission to add tasks.	Stream cannot be imported because the user does not have the permissions to add tasks.
AEM_IMPORT_NO_PERMISSION_ON_ENDPOINT	Failed to import all tasks to replication server {server} as the logged in user does not have permission to add endpoints.	Stream cannot be imported because the user does not have the permissions to add endpoints
AEM_IMPORT_CONTENT_EMPTY	Failed to import all tasks to replication server {server} as the JSON file is empty.	Stream cannot be imported because it contains no content.
AEM_IMPORT_INVALID_CONTENT	Failed to import all tasks to replication server {server} as the JSON file contains invalid content.	Stream cannot be imported because it contains invalid content.

ReloadTable

Reload a specific table.

Required User Role: Operator.

Syntax

```
public void ReloadTable(
    string server,
    string task,
    string schema = null,
    string table = null
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server
task	string	The name of the task
schema	string	The name of the table schema to reload
table	string	The name of the table to reload

Return Values

N/A

Errors

Error	Message	Description
AEM_INVALID_TASK_NOT_FL	Failed to reload table {table} as Full Load is not enabled for task {task}.	The table could not be reloaded because the task's Full Load replication option is not enabled.
AEM_INVALID_TASK_NT_NTSUPPEP	Failed to reload table as this operation is not supported with the File Channel source endpoint.	The table could not be reloaded because the task's source endpoint is File Channel.
AEM_RELOAD_TABLE_ERR	Failed to reload table {schema}. {table} for replication task {task} on server {server}: {message}	An error was encountered while trying to reload the specified table.

TestEndpoint

Connect to an endpoint to test connectivity and configuration (permissions, CDC configuration. etc.).

Required User Role: Operator.

Syntax

```
public AemTestEndpointResp TestEndpoint(
    string server,
    string endpoint,
    int timeout = 60
);
```

Parameters

Parameter	Type	Description
server	string	The name of the server on which the endpoint is defined.
endpoint	string	The name of the endpoint.
timeout	int	Time in seconds to wait until getting a response.

Return Values

AemTestEndpointResp

Parameter	Type	Description
Status	AemEndpointState <pre>{ UNKNOWN = 0, CONNECTED = 1, ERROR = 2 }</pre>	
Message	string	Short description of the error.
DetailedMessage	string	Detailed description of the error.

Errors

Error	Message	Description
AEM_TEST_ENDPOINT_CONNECTION_TIMEOUT	A timeout occurred while testing the connection for endpoint {endpoint} on Replicate server {server}.	Connection was not established within 60 seconds.
AEM_ENDPOINT_NOT_FOUND	Replicate endpoint {0} on server {1} could not be found.	The specified endpoint could not be found.

Parameters

The following table lists all enum parameters that appear in the return values, along with their values.

Parameter Name	Value	Description
Server State	MONITORED	The server is being monitored, the AEM is connected and synchronized successfully.
	ERROR	AEM fails to connect and monitor the server.
	NOT_MONITORED	The server is not being monitored.
Server Platform	» WINDOWS	
	» LINUX	
License State	» LICENSE_VALID	
	» LICENSE_INVALID_CHECKSUM	
	» LICENSE_EXPIRED NO_LICENSE	
	» MACHINE_NOT_LICENSED	
» INVALID_LICENSE		
Endpoint Role	SOURCE or TARGET	Specifies whether an endpoint is being used as a source or a target in a Replicate task.

Parameter Name	Value	Description
Task State	RUNNING	The task is running.
	STOPPED	The task has not been run yet or has stopped running at some point during the replication.
	ERROR	The task has stopped due to a fatal error.
	RECOVERING	The task has detected an error and is trying to recover. After a limited number of attempts, the task either recovers and the state returns to RUNNING, or the task fails and the state turns to ERROR.
Task options	full_load_enabled [bool]	Creates all files or tables at the target endpoint, automatically defines the metadata that is required at the target, and populates the tables with data from the source.
	apply_changes_enabled [bool]	Updates all changes made to files and tables that were created during the full load. Applied changes include inserts, updates, and removal of items.
	store_changes_enabled [bool]	Stores changes in Change tables. This value and the audit_changes_enabled value are mutually exclusive.
	audit_changes_enabled [bool]	Stores changes in a single audit table. This value and the store_changes_enabled_value are mutually exclusive.
Task Stop reason	NONE	Indicates that a task is running and no Stop reason is prevalent.

Parameter Name	Value	Description
	NORMAL	Indicates that the task was stopped by the user.
	RECOVERABLE_ERROR	Indicates that the task is still active, but that there is a temporary problem, such as a missing connection. As soon as the error state is resolved, Replicate restarts the task.
	FATAL_ERROR	Indicates that the task stopped and the error must be resolved manually. The task cannot be started again until the error has been resolved.
	FULL_LOAD_ONLY_FINISHED	Indicates that the task only finished full load.
	STOPPED_AFTER_FULL_LOAD	Indicates that the task stopped after full load. Cached changes may or may not have been applied.
	STOPPED_AFTER_CACHED_EVENTS	Indicates that the task stopped after cached changes were applied.
	EXPRESS_LICENSE_LIMITS_REACHED	The task definition includes actions that are not included with Express license privileges.
	STOPPED_AFTER_DDL_APPLY	Indicates that the task stopped after DDL statements were applied.
	STOPPED_LOW_MEMORY	Indicates that the task stopped due to low memory.
	STOPPED_LOW_DISK	Indicates that the task stopped due to low disk space.
Replication profile	UNIDIRECTIONAL	Data is replicated from a source to a target.
	BIDIRECTIONAL	Changes to the source are replicated to the target, and vice versa.
	LOG_STREAM_STAGING	Changes are captured from a single source and stored on Replicate Server for replication to one or more

Parameter Name	Value	Description
		targets.
Source type		Source and target endpoint types should be specified in the same format that they appear in the Type drop-down list (when adding a new endpoint in AEM). For information on how to add an endpoint in AEM, refer to the <i>AEM Setup and User Guide</i> .
Target type		
Run options	RESUME_PROCESSING	Resumes task execution from the point that it was stopped.
	RELOAD_TARGET	Re-starts the full-load replication process if the task was previously run.
	RESUME_PROCESSING_FROM_TIMESTAMP	Starts the CDC replication task from a specific point.
	RECOVER_USING_LOCALLY_STORED_CHECKPOINT	Recover a task using the recovery state stored locally in the task folder (located under the Data folder).
	RECOVER_USING_CHECKPOINT_STORED_ON_TARGET	Recover a task using the CHECKPOINT value from the attrep_txn_state table (created in the target database).
	METADATA_ONLY_RECREATE_ALL_TABLES	Recreates the target tables defined for full load.
	METADATA_ONLY_CREATE_MISSING_TABLES	Creates missing target tables, including Change Tables.
Request state	SUCCESS	Connection to endpoint is valid
	FAILURE	Connection to endpoint is not valid

4 | AEM Python SDK

This chapter explains how to use the AEM .Python SDK and the lists the available methods.

In this chapter:

[Prerequisites](#)

[How To](#)

[Authentication and Authorization](#)

[Error Handling](#)

[put_server_license](#)

[get_server_details](#)

[put_server](#)

[put_server_acl](#)

[get_server](#)

[get_server_acl](#)

[get_server_list](#)

[delete_server](#)

[delete_server_acl](#)

[get_task_list](#)

[get_task_details](#)

[delete_task](#)

[export_task](#)

[import_task](#)

[stop_task](#)

[run_task](#)

[get_endpoint_list](#)

[delete_endpoint](#)

[export_all](#)

[import_all](#)

[reload_table](#)

[test_endpoint](#)

[Parameters](#)

Prerequisites

General Prerequisites

Before using the AEM Python SDK, make sure that:

- » Attunity Enterprise Manager has been installed.
- » The AEM service is active.
- » The relevant permissions have been granted.

Python 2.7 Prerequisites

1. Add the following files to the **Environment Variables** folder:

- » **C:\python27**

- » **C:\python27\Scripts**

2. Open a command prompt and type the following:

```
pip -v
```

If an error is returned, it means there is an issue with the "Environment Variables"

If the command is successful, type the following:

```
pip install enum34
```

Python 3.7 Prerequisites

Add the following files to **Environment Variables**:

- » **..\appdata\Local\Programs\Python\Python37'**

- » **..\appdata\Local\Programs\Python\Python37\Scripts**

How To

This section describes how to use the AEM Python SDK. To help you better understand how to implement the available methods, a code sample and a readme file that describes the code are located in the **<AEM_Installation_Folder>/clients/python** folder.

To be able to use the AEM.Python API:

1. Import the AEM-Client by adding the following code:

```
from aem_client import *
```

2. Create an aem_client object using the following constructors: (self, b64_username_password, machine_name, port=443, url="https://{0}/attunityenterprisemanager", verify_certificate=True):

- » b64_username_password – You need to create base64 encoded of "domain\\user:password":

- » `domain_username = '{0}\'\'{1}'.format(domain, username)`
 - » `username_password_str = str.encode('{0}:{1}'.format(username, password))`
 - » `b64_username_password = b64.b64encode(username_password_str).decode('ascii')`
 - » `machine_name` - The machine on which AEM is installed.
 - » `port` - The AEM server port (usually 443).
 - » `url` - The URL to the AEM server. If not set then `https://{0}/attunityenterprisemanager` is used where `{0}` is the machine name.
 - » `verify_certificate` - When `verify_certificate` is set to **true**, there must be a valid certificate in the AEM machine. When set to **false**, AEM client will not validate the server certificate. The default is **true**.
- Example: `aem_client = AemClient(b64_username_password, machine_name, verify_certificate=False)`

The user can now use the client methods to get/set data from AEM using the public APIs. For example:

- » `aem_client.get_server_list()`
- » `aem_client.get_server_list()`
- » `aem_client.export_task(server_name, task_name)`

Authentication and Authorization

The `aem_client` user and password need to be the user and password that are defined in users or groups in AEM ACLs in at least one level (e.g AEM level, All Servers level, etc.) with at least Viewer role.

Error Handling

When a REST request fails, the HTTP response code is set to an error code. Information about the error is returned in the payload as an error response.

An error response has the following structure:

Class: `AemClientException` that inherits from `Exception` class and has the following fields:

`error_code`

`message`

This section lists the generic messages that apply to most of the API functions. Errors that are specific to a particular API function appear in the section for that API function.

Error	Message	Description
UNAUTHORIZED_REQUEST	Unauthorized Request.	The user is not authorized to perform the requested action (e.g. deleting a task).
INVALID_SESSION_ID	The session has expired or the session ID is not valid.	Session expired or invalid.
DESERIALIZE_TO_TYPE	Failed to deserialize json to type {type}: {message}	Returned when the JSON format is invalid.
AEM_SERVER_NOT_FOUND	The requested server {server} could not be found.	The requested server cannot be found.
AEM_SERVER_NOT_MONITORED	The requested server {server} is not monitored.	The requested server is not being monitored and thus the information is not accessible.
AEM_SERVER_NOT_CONNECTED	The requested server "{server}" cannot be reached at this time. Message: {message}	The desired information cannot be retrieved as the requested server is not connected.
AEM_SERVER_LICENSE_EXPIRED	The license for requested server {server} has expired.	The requested server license has expired.
AEM_SERVER_INVALID_LICENSE	The license for requested server {server} is not valid.	The requested server license is not valid.
LICENSE_NOT_FOUND	You need to register a Replication Management license in order to use Attunity Enterprise Manager. To register or obtain a license, open the Attunity Enterprise Manager console and follow the instructions.	Replication Management license was not found. For a user who is permitted to Register AEM license.
LICENSE_NOT_FOUND_CONTACT_ADMIN	An Enterprise Manager Admin needs to register a Replication Management license before you can use the product. To obtain a license, contact your Attunity Sales Representative with the Enterprise Manager machine name (which is displayed when you open the Enterprise Manager console).	Replication Management license was not found. For a user who is NOT permitted to Register AEM license.
LICENSE_	{Module} evaluation license has	{Module} is one of the following:

Error	Message	Description
EVALUATION_EXPIRED	expired.	<ul style="list-style-type: none"> » Replication Management » Replication Analytics
LICENSE_TERM_EXPIRED	{Module} license has expired.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
LICENSE_INVALID_SIGNATURE	The {Module} license signature is invalid.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
LICENSE_HOST_MISMATCH	The host name in the {Module} license does not match the Enterprise Manager machine name.	{Module} is one of the following: <ul style="list-style-type: none"> » Replication Management » Replication Analytics
AEM_MISSING_FIELD	The "{fieldName}" field is missing from the request.	When a mandatory field is missing from the request or appears empty

put_server_license

Registers a license on a specific server via AEM.

Required User Role: Admin on the specified server.

Syntax

```
def put_server_license(
    self,
    payload,
    server
)
```

Parameters

Parameter	Type	Description
payload	string	The license to register on the server [stream]. This is the license that was provided by your Attunity Sales Representative. Expected format: Text or JSON. Currently refers to the Replicate license only.
server	string	The name of the server.

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_PUT_SRV_LIC_INNER_ERR	Failed to put license for server "{server}". Error: "{message}"	Returned if AEM encounters an error/exception when trying to register the license on the specified server.
AEM_SRV_LIC_INVALID_FORMAT	The license file format is corrupt.	Returned when the contents of the license file are invalid.

get_server_details

Retrieves details about the specified server.

Required User Role: Viewer.

Syntax

```
def get_server_details(
    self,
    server
```

)

Parameters

Parameter	Type	Description
server	string	The specified server name in AEM.

Return Values

AemGetServerDetailsResp

Value	Type	Description
server_details	AemServerDetails	ReplicateServerDetails or ComposeServerDetails that are inherited from AemServerDetails
configuration		
host	string	The host name or IP address of the Replicate/Compose Server machine.
platform	AemPlatform <pre>{ UNKNOWN = 0, WINDOWS = 1, LINUX = 2 }</pre>	The platform on which the Replicate/Compose Server machine is installed.
port	string	The port through which the Replicate/Compose Server machine is accessed.
user_name	string	The user name for connecting to the Replicate/Compose Server machine.

Value	Type	Description
description	string	The server description.
last_connection	string	The date and time of the last successful sync/retrieval of tasks and messages.
license	ApiLicense	
days_to_expiration	int	The number of days left before the license expires.
expiration	string	The expiration date of the server license.
issue_date	string	When the license was issued.
state	<pre>AemLicenseState { VALID_LICENSE = 0, INVALID_LICENSE_ CHECKSUM = 1, EXPIRED_LICENSE = 2, NO_LICENSE = 3, MACHINE_NOT_ LICENSED = 4, INVALID_LICENSE = 5 }</pre>	The current license state (e.g. valid, expired, etc.).
message	string	The error message if AEM fails to connect to the Replicate/Compose Server machine.
name	string	The name of the server in AEM.

Value	Type	Description
resource_utilization	AemServerUtilization	
attunity_cpu_percentage	int	The sum of CPU percentage of Replicate server and all running tasks processes.
disk_usage_mb	long	The amount of disk space that the server is currently consuming, in MB. This is the sum of disk usage for all tasks on this server.
machine_cpu_percentage	int	The CPU percentage of the machine where Replicate is installed.
memory_mb	long	The amount of memory that the server is currently consuming, in MB. This is the sum of memory usage for all active tasks on this server, excluding stopped tasks.
state	AemServerState <pre>{ NOT_MONITORED = 0, MONITORED = 1, ERROR = 2 }</pre>	The state of the server.
aem_tasks_summary	TaskSummary	
error	int	The number of tasks that encountered a

Value	Type	Description
		fatal error.
recovering	int	The number of recovering tasks
running	int	The number of running tasks.
stopped	int	The number of stopped tasks.
total	int	The total number of tasks, regardless of state.
version	string	The Replicate/Compose Server version.

Notes

- » The return value -1 means N/A.
- » Parameters related to Disk, Memory, Attunity CPU, and Machine CPU usage are not available for Compose servers. For Compose servers, these parameters will be returned as -1.
- » Parameters related to Attunity CPU and Machine CPU usage are only available for Replicate 6.2 and above. For earlier Replicate versions, these parameters will be returned as -1.
- » For servers that are in an error state or not monitored, parameters related to Disk and Memory usage will be returned as -1.

Errors

Error	Message	Description
AEM_SERVER_NOT_FOUND	Replicate server {server} could not be found.	Server name unknown to AEM.

See [Error Handling](#).

put_server

Adds a new Replicate/Compose Server or updates the server definition (Connection Properties) if the specified server already exists. This method can be used together with

AemGetServer in order to update the connection properties of an existing server. First call AemGetServer, then edit the returned properties as required, and finally, call AemPutServer.

Required User Role

- » For adding a new server - Admin on all servers.
- » For updating an existing server - Admin on the specified server.

Syntax

```
def put_server(
    self,
    payload,
    server
)
```

Parameters

Parameter	Type	Description
payload	AemServer	AemReplicateServer or AemComposeServer that is inherited from AemServer
description	string	The server description.
host	string	The host name or IP address of the server.
monitored	bool	Whether to retrieve tasks and messages from this server or not.
name	string	The name of the server.
password	string	The password to connect to the Replicate/Compose Server. Note The password identifier (GUID) that is returned by GetServer is valid only for the session in which it was generated. Using it in another session (for example as input for PutServer) will result in exception.
port	string	The port through which the server is accessed.
username	string	The user name to connect to the Replicate/Compose Server.
server	string	The name of the server.

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
DESERIALIZE_TO_TYPE	"Failed to deserialize json to type AemServer: {message}"	Returned when the JSON format is invalid format. For example, such an error will be returned if the JSON contains an unknown role.
AEM_PUT_SERVER_INNER_ERR	Failed to put server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to PUT the server.
AEM_INVALID_SERVER_TYPE	Server type {ServerType} for server "{ServerName}" is not valid.	Returned when the an invalid server type is specified.
AEM_NAME_URL_MISMATCH	The name of the server in the request does not match the one that is specified in the URL.	Returned when the name of the server in the request does not match the one that is specified in the URL.
AEM_EMPTY_HOST	The host is missing from the request.	Returned when the host is missing from the request.
AEM_EMPTY_PORT	The port is missing from the request.	Returned when the port is missing from the request.
AEM_EMPTY_USERNAME	The username is missing from the request.	Returned when the user name is missing from the request.
AEM_EMPTY_PASSWORD	The password is missing from the request.	Returned when the password is missing from the request.
AEM_INVALID_PORT	The port is invalid.	Returned when the specified port is not valid.
AEM_INVALID_	The user name is invalid.	Returned when the

Error	Message	Description
USERNAME	User names cannot exceed 104 characters and can contain all Unicode characters except for the following characters: Forward slash (/), Left square bracket ([), Right square bracket (]), Colon (:), Semicolon (;), Vertical bar (), Equal sign (=), Plus sign (+), Asterisk (*), Question mark (?), Left angle bracket (<), Right angle bracket (>), Double quote (\").	specified user name is not valid.
AEM_INVALID_DESC	The description is invalid. Descriptions cannot exceed 250 characters.	Returned when the description exceeds 250 characters.
AEM_INVALID_HOST	The host is invalid. Hosts cannot exceed 64 characters and can only contain letters (a-z or A-Z), digits, spaces, dots (.), dashes (-), and underscores (_).	Returned when the server host name exceeds 64 characters or contains invalid characters.
AEM_INVALID_NAME	The name of the server is invalid. Server names cannot exceed 64 characters and can only contain letters (a-z or A-Z), digits, spaces, dots (.), dashes (-), and underscores (_).	Returned when the server name exceeds 64 characters or contains invalid characters.
AEM_HOST_PORT_ALREADY_EXIST	Host {name/IP} and port {number} are already in use by another server.	Returned when both the server host name/IP address and the server port are already in use by another server.

put_server_acl

Puts an explicit ACL for a specific server in AEM. The method will replace any existing explicit ACL with the ACL in the request. The request also includes a Boolean flag for specifying whether or not the server should inherit ACLs from its ancestors (in addition to its explicitly defined ACLs).

The inherited ACLs (i.e., the ACLs of the server's ancestors) are not affected by this method.

The `AemPutServerAcl` can be used together with the `AemGetServerAcl` method in order to update an existing server's ACL. First call `AemGetServerAcl`, then edit the returned roles as required, and finally, call `AemPutServerAcl`.

Behavior when putting a partial request:

When the request body includes only some of the roles (as opposed to all four of them), only the roles specifically defined in the request body will be set on the server; roles that are missing or empty will be inherited, but only if the following are true:

- » The `disable_inheritance` flag is set to "True".
- » The roles that are missing/empty in the request are defined for the ancestors.

Behavior on conflicts:

If the `disable_inheritance` flag is set to "False" and the explicit roles in the request conflict with existing inherited roles, then the explicit roles will take precedence. For example, if the request defines user A as a Viewer on **MyServer** and user A is also defined as an Admin on All Servers, then user A will be defined as an Admin on All Servers but as a Viewer on **MyServer**.

Note The user permissions in AEM are completely independent of the user permissions in Replicate. Consequently, `AemPutServerAcl` will affect the server's AEM user permissions, but will *not* affect Replicate's user permissions.

Moreover, when performing an operation via AEM, the user permissions defined for the server entity in AEM apply, whereas when performing an operation directly via the Replicate Console, the user permissions defined in Replicate apply.

Note Defining the same user/group in different roles is not allowed. However, if the same user or group is defined in different roles but with a different case (e.g. Mike vs. mike or Analysts vs. ANALYSTS), no error will be returned and the strongest role will take precedence.

Required User Role: Admin on the specified server.

Syntax

```
def put_server_acl(  
    self,  
    payload,  
    server  
)
```

Parameters

Parameter	Type	Description
payload	AemAuthorizationAcl	
disable_inheritance	bool	If set to "true", the server does not inherit ACLs from its ancestors (in addition to its explicit ACLs). If set to "false", the server inherits ACLs from its ancestors, in addition to any explicit ACLs
admin_role	AemRoleDef	Users and/or groups assigned as Admin role
designer_role	AemRoleDef	Users and/or groups assigned as Designer role
operator_role	AemRoleDef	Users and/or groups assigned as Operator role
viewer_role	AemRoleDef	Users and/or groups assigned as Viewer role
groups	List<AemGroupRef>	Groups assigned as the role
name	string	The group name
users	List<AemUserRef>	Users assigned as the role
name	string	The user name
server	string	The name of the server

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
DESERIALIZE_TO_TYPE	"Failed to deserialize json to type AemAuthorizationAcl: {message}"	Returned when the JSON format is invalid format. For example,

Error	Message	Description
		such an error will be returned if the JSON contains an unknown role.
AEM_PUT_SERVER_ACL_INNER_ERR	Failed to put ACL of server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to put the server's ACL.
AEM_NO_DOMAIN_IN_USER	User "{userName}" must be preceded by a domain name, separated by a backslash. Example: domain_name\user_name.	Returned when the domain is missing from the user name.
AEM_NO_DOMAIN_IN_GROUP	Group "{groupName}" must be preceded by a domain name, separated by a backslash. Example: domain_name\group_name.	Returned when the domain is missing from the group name.
AEM_NO_ADMIN_ON_SERVER	Requested server "{serverName}" has no admin user. At least one user or group must be assigned to the "admin" role.	Returned when there is no admin on the server. Possible reasons: <ul style="list-style-type: none"> » The request JSON is set to <code>disable_inheritance=true</code> and the explicit admin role in the JSON is empty. » The JSON is set to <code>disable_inheritance=true</code>, the explicit admin role in the JSON is empty, and the parent levels do not have an admin user to inherit.
AEM_USER_ASSIGNED_TO_MULTIPLE_ROLES	User "{userName}" is assigned to multiple roles. Users can only be assigned to a single role.	Returned when a user is assigned to multiple roles.
AEM_GROUP_ASSIGNED_TO_MULTIPLE_ROLES	Group "{groupName}" is assigned to multiple roles. Groups can only be assigned to a single role.	Returned when a group is assigned to multiple roles.
AEM_USER	"{userName/groupName}" is	Returned either when the

Error	Message	Description
GROUP_MULTIPLE_ASSIGNED	assigned to multiple roles or to the same role twice. Users/groups can only be assigned once, and to a single role.	specified user already exists as a group in the same/another role, or the specified group already exists as a user in the same/another role.

get_server

Retrieves the definition (Connection Properties) of the specified server. This method can be used together with PutServer in order to update the connection properties of an existing server. First call GetServer, then edit the returned properties as required, and finally, call PutServer.

Required User Role: Operator on server.

Syntax

```
def get_server(
    self,
    server
)
```

Parameters

Parameter	Type	Description
server	string	The name of the server to retrieve.

Return Values

AemServer (AemReplicateServer or AemComposeServer that are inherited from AemServer)

Value	Type	Description
description	string	The server description.
host	string	The host name or IP address of the server.
monitored	bool	Whether to retrieve tasks and messages from this server or not.

Value	Type	Description
name	string	The name of the server.
password	string	The password to connect to the Replicate/Compose Server. Note The password identifier (GUID) that is returned by GetServer is valid only for the session in which it was generated. Using it in another session (for example as input for PutServer) will result in exception.
port	string	The port through which the server is accessed.
username	string	The user name to connect to the Replicate/Compose Server.

Errors

See [general errors](#).

get_server_acl

Retrieves the explicit ACL defined in AEM for the specified server, including a Boolean indication if ACL inheritance is disabled or enabled for the server.

The method returns the explicit ACL only. In other words, it does not return inherited ACLs.

If all of the servers ACLs are inherited (i.e. no ACL was explicitly defined for the server), an error will be returned indicating that no ACL was found.

This method can be used together with `AemPutServerAcl` in order to update an existing server's ACL. First call `AemGetServerAcl`, then edit the returned roles as required, and finally, call `AemPutServerAcl`.

Required User Role: Operator on the specified server.

Syntax

```
def get_server_acl(
    self,
    server
)
```

Parameters

Parameter	Type	Description
server	string	The name of the server where the ACL is located.

Return Values

AemAuthorizationAcl

Value	Type	Description
disable_inheritance	bool	If set to "true", the server does not inherit ACLs from its ancestors (in addition to its explicit ACLs). If set to "false", the server inherits ACLs from its ancestors, in addition to any explicit ACLs.
admin_role	AemRoleDef	Users and/or groups assigned as Admin role.
designer_role	AemRoleDef	Users and/or groups assigned as Designer role.
operator_role	AemRoleDef	Users and/or groups assigned as Operator role.
viewer_role	AemRoleDef	Users and/or groups assigned as Viewer role.
groups	List<AemGroupRef>	Groups assigned as the role.
name	string	The group name.
users	List<AemUserRef>	Users assigned as the role.
name	string	The user name.

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_GET_SERVER_ACL_INNER_ERR	Failed to get ACL of server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when

Error	Message	Description
AEM_SERVER_HAS_NO_ACL	ACL for server "{server}" could not be found.	Returned if no explicit ACL is defined for the server.

Note A server that does not have its own explicit ACL inherits the ACL from its ancestors. Inherited ACLs are *not* returned by this method.

get_server_list

Retrieves a list of servers under AEM management as well as each server's properties.

Required User Role: Viewer.

Syntax

```
def get_server_list(
    self
)
```

Parameters

N/A

Return Values

AemGetServerListResp

Value	Type	Description
serverList	List<AemServerInfo>	ReplicateServerInfo or ComposeServerInfo that inherit from AemServerInfo.

Value	Type	Description
description	string	The description of the server
host	string	The host name or IP address of the server.
last_connection	string	The date and time of the last successful sync/retrieval of tasks and messages.
message	string	The error message if AEM fails to connect to the server.
name	string	The name of the server.
platform	AemPlatform { UNKNOWN = 0, WINDOWS = 1, LINUX = 2 }	AemPlatform
port	string	The port through which the server is accessed.
state	AemServerState { NOT_MONITORED = 0, MONITORED = 1, ERROR = 2 }	AemServerState
version	string	The Replicate/Compose Server version

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_SERVER_NOT_FOUND	Replicate server {server} could not be found.	Server name unknown to AEM.

delete_server

Description

When this method is called, AEM will:

- » Delete the specified server from AEM
- » Stop monitoring any tasks that were defined on the server
- » Delete all messages related to the server from the Message Center
- » Delete all user roles defined for the server, the server tasks, and the server endpoints

Note The above operations will be performed, regardless of whether the server is currently being monitored or in an error state.

Note

Required User Role: Admin on server.

Syntax

```
def delete_server(
    self,
    server
)
```

Parameters

Parameter	Type	Description
server	string	The name of the server to be deleted.

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Text	Description
AEM_SERVER_	Requested server "{server}"	The server name is unknown to

Error	Text	Description
NOT_FOUND	could not be found.	AEM.
AEM_DELETE_SERVER_INNER_ERR	Failed to delete requested server "{server}".	AEM encountered an error/exception when trying to delete the server.

delete_server_acl

Deletes the explicit ACL defined in AEM for the specified server. Inherited ACLs are not affected by this method. Once the explicit ACL is deleted from the server, all ACLs will be automatically inherited from the server's ancestors.

Required User Role: Admin on the specified server.

Syntax

```
def delete_server_acl(
    self,
    server
)
```

Parameters

Parameter	Type	Description
server	string	The name of the server whose ACL needs to be deleted.

Return Values

N/A

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_DELETE_SERVER_ACL_INNER_ERR	Failed to delete ACL of server "{server}". Error: "{message}".	Returned if AEM encounters an error/exception when trying to delete the server's ACL.

Error	Message	Description
AEM_SERVER_HAS_NO_ACL	ACL for server "{server}" could not be found.	Returned when the specified server has no explicit ACL defined.

get_task_list

Retrieve a list of tasks per selected and authorized server. For each task, the API returns a few values.

Required User Role: Viewer

Syntax

```
def get_task_list(
    self,
    server
)
```

Parameters

Parameter	Type	Description
server	string	The name of the server on which the tasks reside.

Return Values

AemGetTaskListResp

Value	Type	Description
taskList	List<AemTaskInfo>	An array of Endpoint objects.
name	string	The name of the task
state	AemTaskState	<pre>{ STOPPED = 0, RUNNING = 1, ERROR = 2, RECOVERY = 3 }</pre>

Value	Type	Description
	} AemTaskStopReason	
stop_reason	{ NONE = 0, NORMAL = 1, RECOVERABLE_ ERROR = 2, FATAL_ERROR = 3, FULL_LOAD_ ONLY_FINISHED = 4, STOPPED_ AFTER_FULL_ LOAD = 5, STOPPED_ AFTER_CACHED_ EVENTS = 6, EXPRESS_ LICENSE_ LIMITS_ REACHED = 7, STOPPED_ AFTER_DDL_ APPLY = 8, STOPPED_LOW_ MEMORY = 9, STOPPED_LOW_ DISK_SPACE = 10 }	The reason the task stopped
message	string	The message if the task stopped due to an error.
assigned_tags	array	Returns the custom tags assigned to the task. If no tags are assigned to the task, an empty array will be returned.

Errors

See [general errors](#).

get_task_details

Retrieves details about a selected and authorized task. The API returns full monitoring information related to the selected task.

Required User Role: Viewer.

Syntax

```
def get_task_details(
    self,
    server,
    task
)
```

Parameters

Parameter	Type	Description
server	string	The name of the server.
task	string	The name of the task.

Return Values

AemGetTaskDetailsResp

Value	Type	Description
task	AemTaskInfoDetailed	
name	string	The task name.
cdc_event_counters	AemTaskCdcEventCounters	All numeric data concerning CDC events
applied_ddl_count	long	The total number of metadata changes, such as add column
applied_delete_count	long	The number of records deleted in total for all

Value	Type	Description
		tables
applied_insert_count	long	The number of records added in total for all tables
applied_update_count	long	The number of records updated in total for all tables
cdc_latency	AemCdcLatency	CDC latency information
source_latency	string	The time gap between the original change in the source endpoint and capturing it, in hh:mm:ss
total_latency	string	The overall latency (source latency + target latency + apply latency), in hh:mm:ss
cdc_throughput	AemCdcThroughput	Indicates how fast the table records are being replicated to the target endpoint (by number or volume of records). Refers only to the current/last CDC.
source_throughput_records_count	AemCdcThroughputItem	The current source throughput, in rec/sec
source_throughput_volume	AemCdcThroughputItem	The current source throughput, in kbyte/sec
target_throughput_records_count	AemCdcThroughputItem	The current target throughput, in rec/sec
target_throughput_volume	AemCdcThroughputItem	The current target throughput, in kbyte/sec
current	long	
cdc_transactions_counters	AemCdcTransactionsCounters	All numeric data concerning CDC transactions

Value	Type	Description
applied_comitted_transaction_count	long	The number of transactions committed.
applied_records_comitted_count	long	The sum of all records/events in all Completed transactions
applied_records_in_progress_count	long	The sum of all records/events in all In-Progress transactions
applied_transactions_in_progress_count	long	The number of transactions in progress.
applied_volume_comitted_mb	long	The sum of all volume/events in all Completed transactions, in MB.
commit_change_records_count	long	The number of COMMIT change records.
incoming_accumulated_changes_on_disk_count	long	The number of changes accumulated on disk until source commit
incoming_accumulated_changes_in_memory_count	long	The number of changes accumulated in memory until source commit.
incoming_applying_changes_in_memory_count	long	The number of changes in memory during apply and until target commit.
incoming_applying_changes_on_disk_count	long	The number of changes on disk during apply and until target commit.
rollback_change_records_count	long	The number of ROLLBACK change records.
rollback_change_volume_mb	long	The volume of ROLLBACK changes, in MB.

Value	Type	Description
rollback_ transaction_count	long	The number of changes in memory during apply and until target commit.
full_load_completed	bool	
full_load_counters	AemTaskFullLoadCounters	All numeric data concerning Full Load events.
estimated_records_ for_all_tables_count	long	The estimated number of records remaining to be loaded into the target endpoint.
records_completed_ count	long	The total number of records that have completed loading into the target endpoint.
tables_completed_ count	int	The number of tables that have been loaded into the target endpoint.
tables_loading_count	int	The number of tables that are currently being loaded into the target endpoint.
tables_queued_count	int	The number of tables that are waiting to be loaded due to an error.
tables_with_error_ count	int	The number of tables that could not be loaded due to an error.
full_load_end	string	Indicates whether the full load process has ended.
full_load_start	string	The start time of the full load process. Format: YYYY MM DD Timezone: UTC
full_load_throughput	AemFullLoadThroughput	

Value	Type	Description
source_throughput_records_count	int	The current source throughput, in rec/sec.
source_throughput_volume	int	The current source throughput, in kbyte/sec.
target_throughput_records_count	int	The current target throughput, in rec/sec.
target_throughput_volume	int	The current target throughput, in kbyte/sec.
memory_mb	long	The current utilization of memory, in MB. A task's memory utilization is sampled every 10 seconds. When the task is not running, the value is set to zero (0).
cpu_percentage		The current CPU usage of the Replicate task process.
		<p>Notes</p> <p>Only available for Replicate tasks running on Replicate 6.2 and above. When not available, this parameter will be returned as -1.</p>
disk_usage_mb	long	The current utilization of disk space, in MB. A task's disk utilization is sampled every minute.
data_error_count	long	The total number of data errors in all tables involved in the task. The count is affected by data errors and the Reset

Value	Type	Description
		Data Errors option available when you drill down to a task.
options	AemCommonSettings	
apply_changes_enabled	bool	See Task Options .
audit_changes_enabled	bool	See Task Options .
full_load_enabled	bool	See Task Options .
store_changes_enabled	bool	See Task Options .
replicate_profile	AemReplicateTaskProfile	AemReplicateTaskProfile
	<pre> { UNIDIRECTIONAL = 1, BIDIRECTIONAL = 2, LOG_STREAM_STAGING = 3 } </pre>	
source_endpoint	TaskEndpoint	
name	string	The name of the source endpoint.
type	string	The source endpoint type.
target_endpoint	TaskEndpoint	
name	string	The name of the target endpoint.
type	string	The target endpoint type.
state	AemTaskState	The current state of the task.
	<pre> { STOPPED = 0, RUNNING = 1, ERROR = 2, RECOVERY = 3 } </pre>	

Value	Type	Description
	} }	
task_stop_reason	AemTaskStopReason { NONE = 0, NORMAL = 1, RECOVERABLE_ERROR = 2, FATAL_ERROR = 3, FULL_LOAD_ONLY_ FINISHED = 4, STOPPED_AFTER_ FULL_LOAD = 5, STOPPED_AFTER_ CACHED_EVENTS = 6, EXPRESS_LICENSE_ LIMITS_REACHED = 7, STOPPED_AFTER_DDL_ APPLY = 8, STOPPED_LOW_MEMORY = 9, STOPPED_LOW_DISK_ SPACE = 10 } }	The reason the task stopped.
log_stream_staging	string	If the task is writing to/reading from the Log Stream staging folder, the name of the associated Log Stream Staging task will be returned. Otherwise, an empty string will be returned.
assigned_tags	array	Returns the custom tags assigned to the task. If no tags are assigned to the task, an empty array will be returned.
message	string	The message if the task stopped due to an error.

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_TASK_NOT_FOUND	Replicate task {task} on server {server} could not be found.	The task name is unknown to AEM.

delete_task

Deletes the specified task. The task's logs will be deleted only if `deletetasklogs=true` is specified in the URL.

Required User Role: Designer.

Syntax

```
def delete_task(
    self,
    server,
    task,
    deletetasklogs = False
)
```

Parameters

Parameter	Type	Description
server	string	The server where the task is defined.
task	string	The task to be deleted.
deletetasklogs	bool	Whether to delete the task logs or not.

Return Values

N/A

Errors

Error	Message	Description
AEM_TASK_NOT_FOUND	Replication task {task} on server {server} could not be found.	Returned if the task name is unknown to AEM.
AEM_DELETE_TASK_INNER_ERR	Replication task {task} on server {server} could not be deleted due to an error.	Returned if AEM encounters an error/exception when trying to delete the task.
AEM_DELETE_TASK_ERR	Replication task {task} on server {server} could not be deleted due to an error. {2}	Returned if AEM encounters an error when trying to delete the task.
AEM_TASK_NOT_STOPPED	Replication task {task} on server {server} must be stopped before it can be deleted.	Returned if the replication task was running when <code>AemDeleteTask</code> attempted to delete it.

export_task

Export definitions from the selected task on the selected server. The definitions always include task settings, tables/table patterns (include/exclude), table settings and global transformations. The endpoint definition is only exported along with the task definition if `withendpoints=true` is set.

Required User Role: Operator.

Syntax

```
def export_task(
    self,
    server,
    task,
    withendpoints = False
)
```

Parameters

Parameter	Type	Description
server	string	The name of the server on which the task is defined.
task	string	The task to be exported.
withendpoints	bool	Whether or not to export the endpoint definitions as well.

Return Values

Exported task JSON file as a string.

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_METHOD_NOT_SUPPORTED_VERSION	AemExportTask is only supported on Replicate 5.5 or above.	AemExportTask is only supported on Replicate 5.5 or above.
AEM_EXPORT_TASK_NO_PERMISSION_ON_ENDPOINT	Failed to export task {task} from Replicate server {server} as the logged in user does not have permission to access one or both of the task's endpoints.	Export all cannot be carried out because the user does not have permissions on one or more endpoints.

import_task

Import a single task's JSON definitions provided in the request body into the requested server repository on the selected server.

The ImportTask method enables importing all valid JSON definitions provided in the request body.

This includes task settings, tables/table patterns (include/exclude), table settings and global transformations.

Information about endpoints is included if it was included in the JSON file.

When you import a task, Items that existed in the target server before the import and have no new JSON definition in the request body are not modified and not removed. This means that ImportTask provides no way of removing old definitions that are no longer needed.

Required User Role: Designer on relevant task.

If endpoint definitions are included in the JSON definition, a user must also be Designer on the relevant endpoints.

Syntax

```
def import_task(
    self,
    payload,
    server,
    task
)
```

Parameters

Parameter	Type	Description
payload	string	A JSON document to import
server	string	The name of the server to import to.
task	string	Name of the task to import

Return Values

N/A

Errors

Error	Message	Description
AEM_IMPORT_TASK_NO_PERMISSION_ON_ENDPOINT	Failed to import task {task} to replication server {server} as the logged in user does not have permission to add or modify endpoints.	The task cannot be imported because it includes endpoint definitions, and the user does not have permissions to insert endpoints.
AEM_IMPORT_TASK_CONTAIN_ALIEN_ITEMS	Failed to import task {task} to replication server {server} as the JSON file contains unsupported objects.	The task cannot be imported because the stream contains items that cannot be imported (such as remote machines).

Error	Message	Description
AEM_IMPORT_TASK_NAME_DIFFER	Failed to import task {task} to replication server {server} as the JSON file contains conflicting tasks.	The task cannot be imported because the stream contains conflicting tasks.
AEM_IMPORT_TASK_CONTAINS_MULTIPLE_TASKS	Failed to import task to replication server {server} as the JSON file contains multiple tasks. To import multiple tasks, use AemImportAll instead.	The task cannot be imported since the stream contains multiple tasks, and the method can only import a single task.
AEM_TASK_NOT_IMPORTABLE	Failed to import task {task} as the task is running on server {server}. Stop the task and then try again.	Occurs when trying to import a running task.
AEM_IMPORT_TASK_CONTENT_EMPTY	Failed to import task {task} to replication server {server} as the JSON file is empty.	The task cannot be imported as the specified JSON file is empty.
AEM_IMPORT_TASK_ENDPOINT_DIFFER	Failed to import task {task} to server {server} as the endpoint names in the JSON file's "task" and "databases" sections are not the same.	The task cannot be imported as the endpoint names in the specified JSON file's "task" and "databases" sections are different.
AEM_IMPORT_TASK_NO_ENDPOINT_IN_SERVER	Failed to import task {task} to replication server {server} as the {role} endpoint {endpoint} does not exist on the target server.	The task cannot be imported as one of the endpoints specified in the exported JSON file does not exist on the target server.

stop_task

Stops the selected task.

Required User Role: Operator.

Syntax

```
def stop_task(
    self,
    server,
    task,
```

```

        int timeout = 30
    )

```

Parameters

Parameter	Type	Description
server	string	The name of the server.
task	string	The name of the task.
timeout	int	Time in seconds to wait until getting a response.

Return Values

AemStopTaskResp

Value	Type	Description
state	AemTaskState	The current state of the task. <pre> { STOPPED = 0, RUNNING = 1, ERROR = 2, RECOVERY = 3 } </pre>
error_message	string	The description of the error

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_TASK_ALREADY_STOPPED	Replicate task {task} on server {server} is already stopped.	Cannot stop a task that is in Stopped state.
AEM_STOP_	Failed to stop Replicate task {0} on	An error occurred while

Error	Message	Description
TASK_INNER_ERR	server {1}: <{2}>	trying to stop the task.
AEM_STOP_TASK_TIMEOUT	A timeout occurred when trying to stop Replicate task {0} on server {1}	A timeout occurred while trying to stop the task.

run_task

Run the selected task according to the specified option.

Required User Role: Operator.

Syntax

```
def run_task(
    self,
    payload,
    server,
    task,
    option = AemRunTaskOptions.RESUME_PROCESSING,
    timeout = 30
)
```

Parameters

Parameter	Type	Description
payload	AemRunTaskReq	
cdc_position	string	The <code>cdcposition</code> parameter can either be specified inline or in an external JSON file. The format for both is described in below. Required if the option (see below) = <code>RESUME_PROCESSING_FROM_TIMESTAMP</code> or <code>RECOVER_USING_CHECKPOINT_STORED_ON_TARGET</code>

Parameter	Type	Description
server	string	The name of the server on which to run the task.
task	string	The name of the task to run.
option	<pre>AemRunTaskOptions { RESUME_ PROCESSING = 1, RELOAD_ TARGET = 2, RESUME_ PROCESSING_ FROM_ TIMESTAMP = 3, METADATA_ ONLY_ RECREATE_ ALL_TABLES = 4, METADATA_ ONLY_ CREATE_ MISSING_ TABLES = 5, RECOVER_ USING_ LOCALLY_ STORED_ CHECKPOINT = 6, RECOVER_ USING_ CHECKPOINT_ STORED_ON_ TARGET = 7 }</pre>	
timeout	int	The time in seconds to wait for a response.

Return Value

AemRunTaskResp

Value	Type	Description
error_message	string	The description of the error.
state	AemTaskState	The current state of the task. <pre>{ STOPPED = 0, RUNNING = 1, ERROR = 2, RECOVERY = 3 }</pre>

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_TASK_ALREADY_RUNNING	Replicate task {task} on server {server} is already running.	The task cannot be run because it is already running.
AEM_TASK_IN_RECOVERY	Replicate task {task} on server {server} cannot be run as it is in a recovery state.	The task cannot be run because it is in Recovery state.
AEM_WRONG_OPTION_FOR_CDCPOSITION	Replicate task {task} on server {server} cannot be run with cdcposition {position} and option {option}. Change the option to RESUME_PROCESSING_FROM_TIMESTAMP or RECOVER_USING_CHECKPOINT_STORED_ON_TARGET.	When the option Tables are already loaded. Start processing changes from Timestamp is selected in the Advanced Run Options dialog box for a task, the option sent to the API must be RESUME_PROCESSING_FROM_TIMESTAMP.

Error	Message	Description
AEM_CDC_POSITION_ERR_FORMAT	The cdcposition parameter value for Replicate task {task} on server {server} is not in the correct format ('YYYY-MM-DDThh:mm:ssZ').	The cdcPosition parameter must follow this format: YYYY-MM-DDThh:mm:ssZ Parameters: task name and server name
AEM_RUN_TASK_TIMEOUT	Replicate task {task} on server {server} timed out when requested to "Run".	The task does not assume a Running state or any other steady state (error o stopped).
AEM_RUN_TASK_INNER_ERR	Replicate task {task} on server {server} encountered an error when requested to run.	Replicate experienced an error/exception when trying to run the task.
AEM_RUN_TASK_NO_SRC_NO_TRG	Replicate task {task} on server {server} has no source or target endpoints.	Task validation revealed that the task is missing a source and a target.
AEM_RUN_TASK_NO_SRC	Replicate task {task} on server {server} has no source endpoint.	Task validation revealed that the task is missing a source.
AEM_RUN_TASK_TRG	Replicate task {task} on server {server} has no target endpoint.	Task validation revealed that the task is missing a target
AEM_RUN_TASK_NOT_FL_NOR_CDC	Replicate task {task} on server {server} cannot be run without at least one of the replication options enabled (Full Load, Apply Changes, or Store Changes).	Task validation of a unidirectional task revealed that the replication option definition for the task is missing (Full Load, Apply Changes, or Store Changes).
AEM_RUN_BIDI_TASK_NO_FL_NOR_CDC	Replicate task {task} on server {server} cannot be run without at least one of the replication options enabled (Full Load or Apply Changes).	Task validation of a unidirectional task revealed that the replication option definition for the task is missing (Full Load, Apply Changes, or Store Changes).

get_endpoint_list

Retrieves a list of endpoints and their properties for the specified server.

Required User Role: Viewer.

Syntax

```
def get_endpoint_list(
```

```

self,
server
)

```

Parameters

Parameter	Type	Description
server	string	The name of the server on which the endpoints are defined.

Return Values

AemGetEndpointListResp

Value	Type	Description
endpointList	List<Endpoint>	An array of Endpoint objects.
description	string	The endpoint description
isLicensed	bool	Indicates whether the endpoint is licensed on this server.
name	string	The endpoint name.
role	EndpointRole { ALL = 0, SOURCE = 1, TARGET = 2, BOTH = 3 }	The endpoint role: SOURCE or TARGET.
type	string	The endpoint type - for example, Oracle.

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_ ENDPOINT_ LIST_INNER_ ERR	Failed to retrieve endpoints list from Replicate server {name}.	Replicate experienced an error/exception when trying to retrieve the endpoint list.

delete_endpoint

Description

Deletes the specified endpoint. Note that an endpoint can only be deleted if it is not in use by any task.

Required User Role: Designer.

Syntax

```
def delete_endpoint(
    self,
    server,
    endpoint
)
```

Parameters

Parameter	Type	Description
server	string	The server where the endpoint is defined.
endpoint	string	The name of the endpoint to be deleted.

Return Values

N/A

Errors

Error	Message	Description
AEM_ENDPOINT_NOT_FOUND	Replicate endpoint {endpoint} on server {server} could not be found.	Endpoint name unknown to AEM.
AEM_DELETE_ENDPOINT_INNER_ERR	Failed to delete Replicate endpoint {endpoint} from server {server}.	Replicate encountered an error/exception when trying to delete the endpoint.
AEM_ENDPOINT_IS_IN_USE	Replicate endpoint {endpoint} on server {server} cannot be deleted as it is currently in use by one or more tasks.	The Replicate endpoint must be removed from its associated tasks before it can be deleted.

export_all

Export all definitions from the requested server repository on the selected server (server settings, tasks, endpoints, and so on). The definitions are exported to a JSON file.

Required User Role

- » AEM: Admin
- » Server: Admin
- » All Tasks: Designer
- » All Endpoints: Operator

Syntax

```
def export_all(
    self,
    server
)
```

Parameters

Parameter	Type	Description
server	string	The name of the server containing the repository to be exported.

Return Values

Export JSON file as a string.

Errors

Error	Message	Description
AEM_METHOD_NOT_SUPPORTED_VERSION	AemExportAll is only supported on Replicate 5.5 or above.	The method requires Replicate 5.5 or above.
AEM_EXPORT_NO_PERMISSION	Failed to export all tasks from Replicate server {server} as the logged in user does not have permission to export one or	Export all cannot be carried out because the user does not have permissions on one

Error	Message	Description
ON_TASK	more of the defined tasks.	or more tasks.
AEM_EXPORT_NO_PERMISSION_ON_ENDPOINT	Failed to export all tasks from server {server} as the logged in user does not have permission to export one or more of the defined endpoints.	Export all cannot be carried out because the user does not have permissions on one or more endpoints.

import_all

Import the JSON definitions provided in the request body into the requested server repository on the selected server. The ApiImportAll method uses "merge" semantics. In particular: All valid JSON definitions provided in the request body will be imported.

This includes server settings, task settings, endpoints, and other definitions.

Items that existed in the target server before the import and have no new JSON definition in the request body will not be modified and in particular will not be removed. This means that ApiImportAll provides no way of removing old definitions that are no longer needed.

Required User Role

- » AEM: Admin
- » Server: Admin
- » All Tasks: Designer
- » All Endpoints: Designer

Syntax

```
def import_all(
    self,
    payload,
    server
)
```

Parameters

Parameter	Type	Description
payload	string	A JSON document to import
server	string	The name of the server to import to.

Return Values

N/A

Errors

Error	Message	Description
AEM_METHOD_NOT_SUPPORTED_VERSION	AemImportAll is only supported on Replicate 5.2 or above.	The method requires Replicate 5.2 or above.
AEM_IMPORT_NO_PERMISSION_ON_TASK	Failed to import all tasks to replication server {server} as the logged in user does not have permission to add tasks.	Stream cannot be imported because the user does not have the permissions to add tasks.
AEM_IMPORT_NO_PERMISSION_ON_ENDPOINT	Failed to import all tasks to replication server {server} as the logged in user does not have permission to add endpoints.	Stream cannot be imported because the user does not have the permissions to add endpoints
AEM_IMPORT_CONTENT_EMPTY	Failed to import all tasks to replication server {server} as the JSON file is empty.	Stream cannot be imported because it contains no content.
AEM_IMPORT_INVALID_CONTENT	Failed to import all tasks to replication server {server} as the JSON file contains invalid content.	Stream cannot be imported because it contains invalid content.

reload_table

Reload a specific table.

Required User Role: Operator.

Syntax

```
def reload_table(
    self,
    server,
    task,
    schema = None,
    table = None
)
```

Parameters

Parameter	Type	Description
server	string	The name of the server
task	string	The name of the task
schema	string	The name of the table schema to reload
table	string	The name of the table to reload

Return Values

N/A

Errors

Error	Message	Description
AEM_INVALID_TASK_NOT_FL	Failed to reload table {table} as Full Load is not enabled for task {task}.	The table could not be reloaded because the task's Full Load replication option is not enabled.
AEM_INVALID_TASK_NT_NTSUPPEP	Failed to reload table as this operation is not supported with the File Channel source endpoint.	The table could not be reloaded because the task's source endpoint is File Channel.
AEM_RELOAD_TABLE_ERR	Failed to reload table {schema}. {table} for replication task {task} on server {server}: {message}	An error was encountered while trying to reload the specified table.

test_endpoint

Connect to an endpoint to test connectivity and configuration (permissions, CDC configuration. etc.).

Required User Role:Operator.

Syntax

```
def test_endpoint(
    self,
    server,
    endpoint,
```



```

        timeout = 60
    )

```

Parameters

Parameter	Type	Description
server	string	The name of the server on which the endpoint is defined.
endpoint	string	The name of the endpoint.
timeout	int	Time in seconds to wait until getting a response.

Return Values

AemTestEndpointResp

Value	Type	Description
status	AemEndpointState <pre> { UNKNOWN = 0, CONNECTED = 1, ERROR = 2 } </pre>	
message	string	Short description of the error.
detailed_message	string	Detailed description of the error.

Errors

All of the [general errors](#) as well as the errors listed in the table below.

Error	Message	Description
AEM_TEST_ENDPOINT_CONNECTION_TIMEOUT	A timeout occurred while testing the connection for endpoint {endpoint} on Replicate server {server}.	Connection was not established within 60 seconds.
AEM_ENDPOINT_NOT_FOUND	Replicate endpoint {0} on server {1} could not be found.	The specified endpoint could not be found.

Parameters

The following table lists all enum parameters that appear in the return values, along with their values.

Parameter Name	Value	Description
Server State	MONITORED	The server is being monitored, the AEM is connected and synchronized successfully.
	ERROR	AEM fails to connect and monitor the server.
	NOT_MONITORED	The server is not being monitored.
Server Platform	» WINDOWS	
	» LINUX	
License State	» LICENSE_VALID	
	» LICENSE_INVALID_CHECKSUM	
	» LICENSE_EXPIRED NO_LICENSE	
	» MACHINE_NOT_LICENSED	
» INVALID_LICENSE		
Endpoint Role	SOURCE or TARGET	Specifies whether an endpoint is being used as a source or a target in a Replicate task.
Task State	RUNNING	The task is running.
	STOPPED	The task has not been run yet or has stopped running at some point during the replication.
	ERROR	The task has stopped due to a fatal error.
	RECOVERING	The task has detected an error and is trying to recover. After a limited number of attempts, the task either recovers and the state returns to RUNNING, or the task fails and the state turns to ERROR.
Task options	full_load_enabled [bool]	Creates all files or tables at the

Parameter Name	Value	Description
		target endpoint, automatically defines the metadata that is required at the target, and populates the tables with data from the source.
	apply_changes_enabled [bool]	Updates all changes made to files and tables that were created during the full load. Applied changes include inserts, updates, and removal of items.
	store_changes_enabled [bool]	Stores changes in Change tables. This value and the audit_changes_enabled value are mutually exclusive.
	audit_changes_enabled [bool]	Stores changes in a single audit table. This value and the store_changes_enabled_value are mutually exclusive.
Task Stop reason	NONE	Indicates that a task is running and no Stop reason is prevalent.
	NORMAL	Indicates that the task was stopped by the user.
	RECOVERABLE_ERROR	Indicates that the task is still active, but that there is a temporary problem, such as a missing connection. As soon as the error state is resolved, Replicate restarts the task.
	FATAL_ERROR	Indicates that the task stopped and the error must be resolved manually. The task cannot be started again until the error has been resolved.
	FULL_LOAD_ONLY_FINISHED	Indicates that the task only finished full load.
	STOPPED_AFTER_FULL_LOAD	Indicates that the task stopped after full load. Cached changes may or may not have been applied.
	STOPPED_AFTER_CACHED_	Indicates that the task stopped after

Parameter Name	Value	Description
	EVENTS	cached changes were applied.
	EXPRESS_LICENSE_LIMITS_REACHED	The task definition includes actions that are not included with Express license privileges.
	STOPPED_AFTER_DDL_APPLY	Indicates that the task stopped after DDL statements were applied.
	STOPPED_LOW_MEMORY	Indicates that the task stopped due to low memory.
	STOPPED_LOW_DISK	Indicates that the task stopped due to low disk space.
Replication profile	UNIDIRECTIONAL	Data is replicated from a source to a target.
	BIDIRECTIONAL	Changes to the source are replicated to the target, and vice versa.
	LOG_STREAM_STAGING	Changes are captured from a single source and stored on Replicate Server for replication to one or more targets.
Source type	Source and target endpoint types should be specified in the same format that they appear in the Type drop-down list (when adding a new endpoint) in AEM. For information on how to add an endpoint in AEM, refer to the <i>AEM Setup and User Guide</i> .	
Target type		
Run options	RESUME_PROCESSING	Resumes task execution from the point that it was stopped.
	RELOAD_TARGET	Re-starts the full-load replication process if the task was previously run.
	RESUME_PROCESSING_FROM_TIMESTAMP	Starts the CDC replication task from a specific point.
	RECOVER_USING_LOCALLY_STORED_CHECKPOINT	Recover a task using the recovery state stored locally in the task folder (located under the Data folder).
	RECOVER_USING_CHECKPOINT_STORED_ON_TARGET	Recover a task using the CHECKPOINT value from the attrep_txn_state table (created in the target

Parameter Name	Value	Description
		database).
		<div style="border: 1px solid #add8e6; padding: 10px; background-color: #e0f0ff;"> <p>Note This option is only available if the Store task recovery data in target database option is enabled in the Changes Processing Tuning tab of the Task Settings dialog box.</p> </div>
	METADATA_ONLY_RECREATE_ALL_TABLES	Recreates the target tables defined for full load.
	METADATA_ONLY_CREATE_MISSING_TABLES	Creates missing target tables, including Change Tables.
Request state	SUCCESS	Connection to endpoint is valid
	FAILURE	Connection to endpoint is not valid